



# User manual

Version 4.05



# Content

Version 4.05.....	1
V-Control Quick Start.....	8
Concept.....	8
Devices.....	8
New in V-Control 4.....	8
V-Control 4 and old Device Drivers.....	8
Channels.....	9
Tasks.....	9
Cuelists.....	9
Scripts.....	9
Timestrips.....	9
Installation.....	10
User Interface.....	11
Main Window.....	11
The red Lines.....	11
Device List.....	11
Device Variable List.....	11
Command List.....	12
Command Parameter.....	12
Event List.....	12
Tasks.....	12
Cuelist Tasks.....	13
Script Tasks.....	13
Timestrip Tasks.....	13
Toolbar.....	14
Open.....	14
Save.....	14
Save Inc.....	14
Save as.....	14
Run.....	14
Run Task.....	14
Stop Task.....	14
Stop All.....	14
Channel.....	15
Device.....	15
Device Editor.....	15
Add Task.....	15
Playlist.....	15
Joinlist.....	15
Compile All.....	15
Channel Editor.....	16
Serial Channel.....	16
TCP Channel.....	17
UDP Channel.....	17
SMTP Channel.....	17
Http and Https Channel.....	18
Device Setup.....	19

Device Editor.....	20
Options.....	21
System.....	21
Remote Services.....	22
TCP Remote.....	22
UDP Remote.....	23
HTTP Remote (Webserver):.....	23
RS232 Remote.....	24
The Script Editor Page.....	25
Cuelist Tasks.....	26
Multitasking and blocked Devices.....	26
Cuelists.....	26
Create Cuelists.....	26
Send commands Synchronous to more then one Device.....	28
Edit a Cue.....	29
Non Device Commands.....	29
Wait For Variable.....	30
Repeat.....	32
Delay.....	33
Call as Function.....	34
Call as Thread.....	35
Stop Task.....	36
Stop All Tasks.....	36
Show Message.....	36
Comment.....	37
Shell Execute as Function.....	38
Shell Execute as Thread.....	38
Scripts.....	39
Create Scripts.....	39
IOResult.....	41
Delay.....	41
Call As Function.....	42
Call As Thread.....	43
Stop Task.....	44
Show Message.....	45
Local Variables.....	45
Global Variables.....	48
Shell Execute As Function.....	50
Shell Execute As Thread.....	51
Compiler.....	52
Basic Language Reference.....	52
Abs.....	52
Acos.....	52
Asc.....	52
AscB.....	53
Asin.....	53
Atan.....	53
Atan2.....	53
BitAnd.....	54
BitOr.....	54

BitXor.....	54
BCDToTCString.....	54
Ceil.....	55
ChangeCMD_MinMax.....	55
CheckSum8Bit.....	55
CheckSumMod255.....	55
checksumXOR.....	55
CRC16.....	56
Chr.....	56
ChrB.....	56
Const.....	57
Cos.....	57
CountFields.....	57
CRC16.....	58
Delay.....	58
Exit.....	58
Exp.....	59
FloatStringToStr.....	59
Floor.....	59
For...Next.....	59
Format.....	60
FramecodeToTimecode.....	62
GetDayOfMonth.....	62
GetDayOfWeek.....	62
GetDeviceVar.....	62
GetGlobalVar.....	62
GetHour.....	62
GetMinute.....	63
GetMonth.....	63
GetTime.....	63
GetSeconds.....	63
GetYear.....	63
Hex.....	63
HexToStr.....	64
If...Then...Else.....	64
InStr.....	65
InStrB.....	65
Left.....	65
LeftB.....	65
Len.....	66
LenB.....	66
Log.....	66
Lowercase.....	67
LTrim.....	67
Max.....	67
Microseconds.....	67
Mid.....	68
MidB.....	68
Min.....	68
msToTimecode.....	69

Nil.....	69
NthField.....	69
NthFieldB.....	70
Oct.....	70
Pow.....	70
Redim.....	70
Rem.....	71
Replace.....	71
ReplaceB.....	71
ReplaceAll.....	72
ReplaceAllB.....	72
Right.....	72
RightB.....	72
Rnd.....	73
Round.....	73
RTrim.....	73
Select Case.....	73
SetDeviceVar.....	74
SetGlobalVar.....	75
Sin.....	75
SingleToStr.....	75
Sqrt.....	75
Str.....	76
StrComp.....	76
StrToHex.....	76
Tan.....	77
Ticks.....	77
TimecodeToFramecode.....	77
Titlecase.....	77
Trim.....	77
Ubound.....	78
Uppercase.....	78
Val.....	78
Compiler Errors.....	79
Timestrips.....	81
Timestrip user interface.....	81
Create Timestrip.....	82
Chase Devices.....	83
Events.....	86
Device Variable Change Events.....	86
The Condition Script.....	88
The Condition Editor.....	88
Calendar Events.....	89
Simple GUI.....	91
Playlist.....	91
CallButtons.....	92
V-Control Designer.....	93
Installation.....	93
Remote Panel Server.....	93
V-Control Designer.....	93

Licensing.....	93
Hardware License Key.....	94
Remote Panel Server.....	95
Join Number Concept in Detail.....	96
Manage Join Numbers.....	99
GUI Overview.....	100
Project Settings.....	101
Settings.....	102
Pages.....	102
Buttons.....	103
Progress Bar.....	104
Label.....	105
Group Box.....	106
Image.....	107
Text Input.....	108
Combo Box.....	109
Slider.....	110
Ellipse.....	111
Rectangle.....	112
RemoteScreenSender.....	113
Sending Device Variables.....	113
Sending User Data.....	116
Getting Join Values.....	116
RemoteScreenReceiver.....	117
System.....	117
Web Server.....	118
Language / IDE of your Choice.....	119
Device Editor.....	120
Parameter.....	120
Command Types.....	125
Create New Driver.....	125
Simple Commands.....	126
Complex Commands.....	130
Hep Text.....	133
Monitor and Acknowledge Comands.....	134
Monitor Commands.....	135
Ack(nowledge) Commands.....	136
Automatic Parameters.....	137
Events.....	140
Export Device Driver.....	141
Import Device Driver.....	141
Device Drivers.....	142
System.....	142
V-Control Connectors.....	143
MIDI.....	143
Art-Net.....	145
Main GUI.....	145
Preferences.....	146
New Scene from Output.....	148
New Scene from Input.....	149

Use with V-Control.....	149
Tools.....	150
Hex/Bin/Dec/ASCI conversion.....	150
Remote Protocol.....	151
TCP, UDP and RS232 Message Format.....	151
Websocket Message Format.....	151
Start of Transmission.....	151
Msg Type.....	152
Separator.....	152
CMD.....	152
Parameter.....	152
End of Transmission.....	152
Web Interface.....	152
HTTP Message Format.....	153
Examples.....	154
TCP/UDP/RS232 Examples.....	154
HTTP Examples.....	154
Device Manager.....	154
Script Manager.....	156
Change Log.....	157
Version 4.6 (JUNE-2018).....	157
Version 4.4 (MAY-2018).....	157
Version 4.3 (FEB-2018).....	158
Version 4.0 (NOV-2017).....	158

# V-Control Quick Start

## Concept

V-Control is designed to control devices. A device can be anything that has a control interface. Typical control interfaces are serial (RS232, RS422 and RS285), Network (TCP, UDP or HTTP), MIDI, DMX, dry contacts, wet contacts etc.

So, from small sensors up to large LED screens you can control anything with V-Control.

## Devices

The philosophy is to have a virtual device in V-Control for each real device that is being controlled. The virtual device (in V-Control its the device driver) is a representation of the real device.

To control the device, a device driver has commands. A command can be a Play command for a player, or an input switch for a projector. V-Control has many device drivers build in, and if one uses one of those drivers, there is no need to know what exactly has to be send to the device to perform the command. The driver offers a command such as "Switch Input to DVI", and it generates the necessary string and send it to the device.

## New in V-Control 4

The (virtual) device driver requests the status of the controlled device and offers commands to control it. The status of a device is represented by device variables. A projector for example can have a variable for Power state, showing if the projector is switched on and of. And a second variable for Input, showing which input is currently selected. The number of device variables depends on the device itself and is not limited.

To act on variable changes we create event handlers. Event handlers are listed in the Event List. Here we create a condition, and if the condition is true, the task that is linked to the event is executed.

## V-Control 4 and old Device Drivers

Some of the V-Control 3 drivers will not compile on V-Control 4 (All that make use of "NextCmd" and "Delay"). In our Driver Database, most of the drivers work in V-Control 4. We marked some drivers with a "\_v3" or "\_v4" extension.

- Drivers without extension work with Version 3 and 4, but do not benefit from V-Control 4 capabilities. They are used in the same way as in V-Control 3
- Drivers with "\_v3" extension work only in V-Control 3 and need an update
- Drivers with "\_v4" extension work only in V-Control 4



## Channels

A channel is a physically present communication interface, such as RS232, TCP, UDP etc. A channel is the object that is used to talk to the device that is attached to the V-Control PC. A Device in V-Control doesn't care what kind of channel is used. You can send the same command via RS232 or TCP, it depends only which channel is assigned to the device. To configure channels for a project use the Channel Editor

## Tasks

Tasks are a group of commands. The simplest type of task is a cuelist. A task should be only a part of the whole show. You can compare tasks with functions, methods or subs in other programming languages. A task is always running in its own thread.

## Cuelists

V-Control knows three types of tasks. A cuelist is just a list of cues. If a cuelist is started it runs from top to bottom and executes the commands in the list. Cuelists only know a limited number of branch commands such as "Repeat", "CallAsFunction" or "CallAsThread". Because a cuelist is limited in flexibility, it is very easy to use, and most of the work can be done in cuelist.

## Scripts

Scripts have all the power one may need for complex tasks. They are programmed in basic, but compile before running.

## Timestrips

Timestrips are comparable to timelines, but the representation is a table.

**Any type of task can call any type of task. In a cuelist task one can call a script task or a timestrip task and vice versa.**

# Installation

The installation is very easy on all supported platforms. Unpack the compressed file in any directory where the user has **write access** (**not** c:\Program Files or c:\Program Files (x86)) and launch the binary file. On Linux, it might be necessary to set the file permissions to allow execution.

On Raspberry Pi, libunwind8 is needed. Open a terminal and type

```
sudo apt-get install libunwind8
```

On Linux and Raspberry Pi it might be necessary to make the V-Control4\_Lin file executeable.

**Uninstallation: Delete the program directory, that's all.**


# User Interface

## Main Window

The V-Control user interface provides quick access to all configured devices, tasks and Events. All the three programming modes, as there are Cuelists, Scripts and Timestrips, are accessible within one user interface.

The selected kind of Task (Cuelist, Script or Timestrip) is determined by the tab bar in the lower half of the application window.

All three programming modes can be used together and mixed within one project.



## The red Lines

These lines are used to change the position and size of the GUI elements. Click and drag the lines to change the GUI.

## Device List

A list of all available configured devices.

## Device Variable List

Each device can have a set of variables. Variables are used to represent the state of the device. They are usually filled automatically from the device itself. If a variable change, this can trigger an action.

## Command List

The command list contains all the available commands. If a command is selected it can show parameters for the command.

## Command Parameter

Most devices and commands need parameters. A parameter can specify a device property (e.g. a bus address or name) or a command parameter such as *Input Channel* to change the input of a device. In V-Control, each command can have up to 6 parameter, two device parameters and four command parameters.

## Event List

Here are all programmed events located. If a device variable change (that can be a new Timecode position during playback of a video player, an input change of a projector or a system time change) this event can be linked to a task. Each event that you want to handle is listed here.

Event List		Search:				
ID	Device	Var Na...	Condition	Task		Block

In complex project the eventlist can be quite long. To help finding events for debugging there is a search field. If text entered here matches any of a row content, then only these rows are displayed.

## Tasks

Task is a generic name for V-Control scripts. A task represents a program or subroutine. They contain the instructions for the attached devices (e.g. play a movie) and the program flow. V-Control knows three different types of tasks, Cuelists, Scripts and Timestrips (Timeline like). To access the tasks, select one of the tabs at the bottom

## Cuelist Tasks

Engine Event Message Stack: -1		IO Queue 0	Pending Acks 0
Cuelists Scripts Timestrips			
Cuelists			
Pause5	0	V7300_1	v7300_1 CueUp
Start6	1	V7300_2	v7300_2 CueUp
Pause6	2	V7300_3	v7300_3 CueUp
Start7	3	V7300_4	v7300_4 CueUp
Pause7	4	V7300_5	v7300_5 CueUp
Start8	5	V7300_6	v7300_6 CueUp
Pause8	6	V7300_7	v7300_7 CueUp
StartAll8	7	V7300_8	v7300_8 CueUp
CueUp8	8	V7300_1	v7300_1 Play
test	9	V7300_2	v7300_2 Play
Start_1	10	V7300_3	v7300_3 Play
Start_2	11	V7300_4	v7300_4 Play
Start_3	12	V7300_5	v7300_5 Play

RemoteUsers saved

These tasks are very easy to use but have some limitations. Every program step is written in a table, and the table is executed from top to bottom. Branching is possible if calling other tasks from that list (CallAsThread, CallAsFunction). Conditional branching is available in Scripts only. Also (nested) repeats are possible. The biggest advantage of Cuelists is, that programming skills are unnecessary to work with them. Also for people with (basic) programming skills, Cuelists lead to target very fast.

## Script Tasks

Scripts are real (and for the chosen platform native compiled) basic programs. In V-Control, the basic language is enhanced by commands giving access to the device drivers and channels.

Engine Event Message Stack: -1	
Cuelists Scripts Timestrips	
Scripts	
CheckLampHours	<pre>RunCmd("EpsonProjector","proj1","GetLampHours"," "," "," "," "," ") if IOResult &gt; 5000 then     RunCmd("RemoteScreenSender_v4","rmt_scrn_sender","SendString"," "," ","4","Lamp Hour Warning"," ") end</pre>

The screenshot below shows the Script GUI.

## Timestrip Tasks

Engine Event Message Stack: -1	
Cuelists Scripts Timestrips	
Timestrips	
Example	<div><div>Absolute Offset Position: Add Position Relative Offset: + 00-00-00-00</div><div>-1M -1S -1F 00-00-43-12 +1F +1S +1M Run from current TC <input type="checkbox"/> Loop</div><div><div>Time Track 1</div><div>00-00-40-00 ioLogic_E1214_v4 io SetSingleRelay "0","3","ON"," "</div><div>00-00-43-12 EpsonProjector proj1 Mute "","OFF"," "</div></div></div>

Timestrips are used for a timeline like programming. The difference is that the

representation of the task is not a timeline, but a table.

## Toolbar



### Open

Opens a Project

### Save

Saves a Project. The saving process is running on it's own thread in the background. It is not possible to terminate V-Control while a saving process is running.

### Save Inc.

Saves a Project with an incrementing number. If the project name is "myProject.vc4", then pressing this button saves "myProject\_001.vc4". Pushing the button a second time saves "myProject\_002.vc4" and so on. **Attention:** *Save Inc.* overwrites existing files without asking. To avoid this, make sure that you always open the project with the largest number after V-Control is launched.

### Save as

Saves a Project under a new name

### Run

This button toggles. If unpressed, V-Control does not send or receive any commands. If pressed, V-Control will perform all events and commands.

### Run Task

Runs a selected task. *F5* key does the same (only available in Run mode).

### Stop Task

Stops the selected task. *F6* key does the same (only available in Run mode).

**Note:** This Action stops the selected task, but if the task is re-executed by an event, then it runs again.

### Stop All

Stops all running tasks. *F7* key does the same (only available in Run mode).

**Note:** This Action stops all tasks, but if a task is re-executed by an event, then it runs again.

## **Channel**

Opens the Channel Editor

## **Device**

Opens the device setup page. Here a device driver can be selected from the device database.

## **Device Editor**

Opens the Device Editor

## **Add Task**

Creates a new task. The type of task (Cuelist, Script or Timestrip) is determined by the task tab that is visible at that moment.

## **Playlist**

Opens a playlist to drive a show.

## **Joinlist**

To receive button presses from external GUI's running on a tablet or PC, and to update GUI elements such as labels, buttons etc. V-Control uses Join Numbers to identify these widgets. In complex project there can be hundreds of widgets, and some widgets can have multiple join numbers. This list can help to keep the overview of all those numbers.

## **Compile All**

**V-Control scripts are compiled once automatically on their first start. This button does the same for all scripts before they run the first time.**

# Channel Editor

Basis for the communication with attached devices are the channels. A channel gives access to a physically interface - e.g. a RS232 port or a UDP port. The device drivers use these channels to communicate with the devices attached to the channels.

Configure Channel Environment

Channels:

Name	Type	Parameter
io	UDP	192.168.1.54...
proj1	UDP	192.168.1.54...
rmt_scrm_se...	UDP	192.168.1.54...

Interface Type

☐ Serial ☐ TCP Client ☒ UDP ☐ http ☐ https

Channel Name:

☐ SMTP (Send Mail)

Serial

Refresh Get Serial List

Port:

Baud:

DataBits:

StopBits:

Parity:

☐ XON ☐ CTS ☐ DTR

TCP/IP

Port:

Address:

UDP

Port:

Router Hops:

Target IP:

SMTP

Server:

From Addr.:

Username:

Password:

https

Port:

Address:

Mode:

User:

Password:

http

Port:

Address:

Mode:

User:

Password:

Delete Channel Update Channel Add Channel


Via main menu *Configure - Channels* (or toolbar shortcut) the channel editor opens. Every channel is identified by its Channel Name. For that reason, not only interface parameters are needed to specify the channel, but also a unique channel name. The channel name should (but is not required) give a hint on how the channel is used. E.g. a channel used to control a Panasonic projector could have the name "proj1\_left", the channel for the second Projector is named "proj2\_right" and so on. We recommend to name the channels in lower case letters, and the Devices with a leading upper case letter.

Before creating a new channel, it is necessary to specify its kind in the Interface Type area and enter a channel name as described above. To edit a channel, select its name in the left list and change its parameters. Then click Update Channel.

## Serial Channel

Serial channels are used for RS232/422 and 485 interfaces. Get Serial List loads all previously scanned ports in the Port: list. If new serial ports attached to the system, Refresh executes a new port scan. On systems with many serial interfaces this could take a while.






Serial configuration window showing the following settings:

- Buttons: Refresh, Get Serial List
- Port: COM3
- Baud: 9600
- DataBits: 8
- StopBits: 1
- Parity: none
- Checkboxes: ☐ XON, ☐ CTS, ☐ DTR

## TCP Channel

To control devices via TCP, the Port and IP Address is needed




TCP Channel configuration window showing the following settings:

- Protocol selection: ☒ TCP Client, ☐ UDP, ☐ http, ☐ SMTP (Send Mail)
- Name: rmt\_scrn\_sender
- Buttons: Get Serial List
- Port: [Empty text box]
- Address: [Empty text box]

## UDP Channel

Router Hops determine how many routers the UDP packet is allowed to pass.




UDP Channel configuration window showing the following settings:

- Port: 1235
- Router Hops: 2
- Target IP: 192.168.1.54

## SMTP Channel

The SMTP channel specifies a mail server. This channel is used by the SMTPMailClient device to send emails.



SMTP

Server:


From Adr.:

Username:

Password:

Server: The mail server (e.g. smtp.web.de) From Adr.: The sender address (me@myspace.com) Username: Username to log in Password: Mail server password

## Http and Https Channel



https

Port:

Address:

Mode:

User:

Password:

http

Port:

Address:

Mode:


User:

Password:

**HTTP and HTTPS channels can automatically log in if username and password is saved in the channel properties. They both can do http Get and Post requests.**


# Device Setup

To configure the devices select *Configure - Devices* in main menu (or *Device* shortcut in the toolbar ). The Device Setup window opens as shown below. The right table lists all devices currently available in the project. The left table list device templates, whose search criteria matches one of the fields Category, Type or Manufacturer.



If the desired driver appears in the left list, a double click or *Add Device* adds the device to the right list (project devices). *Save Devices* saves the right list and make the devices available.

Before the device is usable, it is necessary to assign at a Channel. To do that, follow the instructions in the screenshot below.



1. Select the device in main windows device list
2. press the setup tab (right from commands tab)
3. in the *Available Channels* list select the channel to assign to the selected device

4. press the *Add* button

## Device Editor

It is possible to customize (if needed) the device drivers for a project. A complete description how to create and edit device drivers is found in the Device Editor chapter. In most cases it should be sufficient to change the device name. To do that, follow the instructions below.

The Device Editor is launched via *Device Edit* symbol in the toolbar or main menu *Configure -> Edit Devices...*

The screenshot shows the 'Device Editor' window with a 'Driver' tab selected. The 'Device' section includes fields for ID (4), Device GUI (Standard), Device Name (PanasonicPT\_Series), Type (PanasonicPT\_Series), Manufacturer (Panasonic), Category (Projector), and Name (PanasonicPT\_Series). There are buttons for 'Add Device', 'Update Device', 'Delete Device', 'Add Variable', and 'Delete Variable'. The 'Commands' section shows a list of commands (001 Power, 002 Freeze, 003 Shutter, 004 InputSelect, 005 OnScreenDisplay) and a 'Power' command being edited. The 'Power' command has a Name field, Position (1), Type (Command), and a script area containing VBScript code. The 'Script' area shows: 

```
Dim s as string
if len(DP1) < 2 then DP1 = "0" + DP1
if P1 = "On" then
    s = "PON"
else
    s = "POF"
end
scriptresult = chr(2)+"AD"+DP1+";"+s+chr(3)
```

 The right side of the window shows configuration for four parameters (P1, P2, P3, P4) with fields for Name, GUI, MinMax, Default, and Mask. There are also buttons for 'To Hex', 'To ASCII', and 'Compile'.

To change a device name enter / edit the name in the *Name* textfield. The device is selected in the Drop Down Box *Device*:. *Update Device* saves the new name in the current project.

**The device Editor knows two modes. If launched via *Configure -> Edit Devices* or the *Device Edit* toolbar icon, all changes made in any driver stored in the project (\*.vc4 file). The original driver template stay untouched. If launched via *Configure -> Edit Device Templates*, the template is edited, and the project devices stay untouched. This is important to keep in mind if editing device drivers.**

# Options

Via main menu *Configure -> Options* the program preferences are available.

The screenshot shows the 'Options' dialog box with the 'System' tab selected. The dialog has three tabs: 'System', 'Remote Services', and 'Script Editor'. The 'System' tab contains the following settings:

- ☐ Start delayed to load drivers first
- ☐ Compile all after loading a Project
- Autoload Project: [Empty text box] and [Select Autoload File... button]
- Autostart Task: [Empty text box] and [Select Autostart Task... button]
- ☒ Show Engine Status
- Engine Status Refresh Time (ms): [80 text box]
- Maximum Channel Buffer Size: [500 text box]
- ☒ Show WaitForVariable Countdowns
- Global Framerate: [25 dropdown menu]
- ☐ Modal Playlist Dialog
- Playlist Textsize: [12 spinner box]
- Log Level: [3:Errors dropdown menu]
- ☐ Log to File
- [Delete Logfile button]
- Information text: 'The Logfile is located in V-Control's program directory and is named Logfile.txt'

An 'OK' button is located at the bottom right of the dialog.

## System

- *Start delayed to load drivers first:* If V-Control runs stand alone and is started at system start automatically, it could be that network drivers or drivers for serial cards are not loaded when V-Control is ready. With this option V-Control starts and the waits before loading a project file.
- *Compile all after loading a Project:* All Scripts, device Drivers and Event Scripts have to be compiled before they can run. This happens “on the fly” if a script runs the first time. On weak machines such as Raspberry Pi or slow X86 machines this could lead to missing events or slow processing if a script runs for the first time. To avoid this, this option compiles all scripts after a project was loaded. Depending of the amount of devices, events and tasks, this could take some time. The status bar shows a progress message.

- **Select Autoload File:** selects a file that is load during startup.
- **Autostart Task:** launch the selected task if the Autostart File was loaded.  
**Note:** Only if an *Autostart Task* is selected, V-Control switches to Run Mode automatically. If you don't need a task running at startup, but want to enter Run Mode automatically, create a task that does nothing and select it here.
- **Show Engine Status:** If checked, the load of the control engine is displayed in the main UI. *Engine Event Message Stack* shows the number of messages that are waiting for processing. *IO Queue* shows the number of commands in the command buffer waiting for sending. *Pending Acks* shows the number of Acknowledges the engine is waiting for. *Pending Channel Events* shows the number of Events waiting for processing.
- **Engine Status Refresh Time:** Determines how often the GUI is updated with Variables and logging messages. Keep this at the default value unless you have a good reason to change this.
- **Maximum Channel Buffer Size:** Determines the input buffer of a channel. If a channel receives data, and this data is not processed, the input buffer will continuously grow. This value determines when the buffer is cleared.
- **Show WaitForVariable Countdowns:** If a *WaitForVariable* command waits for a numeric or time value, and the comparison is  $>$ ,  $>=$ ,  $<$  or  $<=$ , then a window with a countdown appears.
- **Global Framerate:** This framerate is used in the Timeline. The framerate is also used in Timecode calculations.
- **Modal Playlist Dialog:** by default, the playlist is no modal dialog (means that you can access other V-Control elements while the playlist is open). If this is checked the playlist is modal. This is useful if keyboard shortcuts are mapped to playlist items and you don't want the playlist to lose its focus.
- **Playlist Textsize:** changes the font size of the Playlist.
- **Logging Level:** determines how many log entries are generated. Default is 3 (only errors). Level 2 is warnings (Timeouts), Level 1 is commands and level 0 is also all internal commands for device status acquisition. With loglevel 0 you'll get a rapidly filling list. The log window opens automatically if a new logmessage corresponding to the selected loglevel appears.
- **Log to File:** writes all messages to a textfile

## Remote Services

Remote Services are used to make V-Control functions available for other applications. They can use Ethernet (TCP/UDP/HTTP) or RS232 to communicate with V-Control. The communication protocol is described in the Node Protocol chapter. To make Remote Services available via network, it might be necessary to configure the firewall of the System. All kind of remote services described below can be used at the same time.

### TCP Remote

The TCP service can be used by any application that is capable to connect to a

TCP Server and send the command strings as described in the Node Protocol chapter. The Port is 10101 by default and can be changed. Max Clients determines the maximum number of simultaneously connected clients. The check-box *Enable TCP Remote Service* starts the service.

TCP

UDP

HTTP

RS232

User Management

Port:

10101

Max Clients:

5

☐ Enable TCP Remote Service

## UDP Remote

The UDP Service uses the same protocol than the TCP Service. If both services used at the same time, it is necessary to use a different port. For that reason, the default UDP Port is 10102.

TCP

UDP

HTTP

RS232

User Management

Port:

10102

☐ Enable UDP Remote Service

## HTTP Remote (Webserver):

V-Control comes with a built-in web server.

System Remote Services Script Editor

TCP UDP HTTP RS232 User Management

Port: 8080  
Max Clients: 5  
Documents Root Dir:   
Local Server URL: http://192.168.1.25:8080  
☐ Enable HTTP Service

The HTTP Port is 80 by default. In this case it is sufficient to enter the IP address of the V-Control system in the browsers address field. If the web service is not available, check the firewall configuration of the computer or try another port. If another port than 80 is used, the port number has to be added to the URL (e.g. http://192.168.1.5:8080) if Port 8080 is used alternatively. *Documents Dir* contain the path to the html documents directory.

## RS232 Remote

If there is no network available, it is possible to use a RS232 connection. The RS232 service uses the same protocol than TCP or UDP services.


System Remote Services Script Editor

TCP UDP HTTP RS232 User Management

Commport:   
Baudrate: 9600  
Data Bits: 8  
Stop Bits: 1  
Parity: none  
☐ Enable RS232 Remote Service



# The Script Editor Page



This dialog is used to configure the Script Editor

- **Color Syntax:** Switch Color Syntax on / off
- **Keywords:** Basic keywords are marked blue
- **Numbers and Strings:** These values marked green.
- **Remarks:** Code lines containing *are marked red from the occurrence of the letters*
- **Textsize:** The size of the font
- **Font:** The type of the font

# Cuelist Tasks

Tasks contain the instructions for the attached devices and the program flow. V-Control knows three types of tasks, Cuelists, Scripts and Timestrips. Cuelists are very easy to use without real programming. Scripts contain (native compiled) Basic scripts, which makes them very powerful for all kind of applications. Timestrips are a kind of timeline and can be useful in Show Control.


## Multitasking and blocked Devices

V-Control can run many tasks at the same time. If multiple tasks running together, the programmer has to take care that not more then one task at a time is using the same resource. A resource is a channel or a device.

If one task is accessing a device, and another task wants to access the same device at the same time, the first task wins, the command of the second one is stored in a queue and performed if the device is free.

## Cuelists


In Cuelists, the commands stored in a table that is processed from top to bottom. It is possible to branch to other tasks and call them as function or thread, but conditional branching is available in Scripts only.




ID	Device	Channels	Command	Parameter
0	DVS_Pronto	pronto	CueUp	
1	DVS_Pronto	pronto	Play	
2	DVS_Pronto	pronto	WaitForVariable	DVS_Pronto.Position < 01-04-01-12
3	DVS_Pronto	pronto	Stop	
4			CallAsFunction	OutroLights

## Create Cuelists

To Create a Cuelist, select Cuelists in the Task area.



Then select *Tasks* -> *Add* in main menu or via Cuelist context menu (right click) select *Add Task*. Alternatively the *Add Task* tool button or Ctrl+A does the same job.



Each task needs a unique name that is entered in the dialog box as shown above. Then we have a new (Cuelist) task that is selectable and ready to take the instructions.

So lets add the first command. In the *Device List* select a device (PJLink in this case). Select a Command in the *Command List* (SetInputVideo here) and change the parameter to match your needs. Click the *Add Cmd* button to add the command in the list.

The screenshot shows the main software interface with the 'Commands' setup window open. The 'Device List' on the left includes 'PJLink'. The 'Command List' in the center has 'SetInputVideo' selected at position 011. The 'Input' parameter is set to '1'. The 'Add Cmd' button is visible. Below the window, the 'Cuelists' table is shown with the following data:

Cuelists	ID	Device	Channels	Command	Parameter
Start_1	0	PJLink	pjlink	SetInputVideo	
Start_2	1				
Start_3					
Start_4					
Start_5					
Start_6					
Start_7					
Start_8					
Start_All					
Test Relais					
TestVP					
SendPos2					
MyBrandNewTask					

The next command is a CueUp instruction for a Player. Same procedure here. Select the Device, select the command, enter a parameter and click *Add Cmd*.

The screenshot shows the software interface with the following components:

- Devices:** HSW\_Dreh scheiben\_Mon, PJLink, ioLogik E1214, HSW Dreh scheiben Monit..., V7300\_1 (selected), V7300\_2, V7300\_3, V7300\_4, V7300\_5, V7300\_6, V7300\_7, V7300\_8, RemoteScreenRec, RemoteScreenSender, System\_v4\_1216.
- Var Name / Value:** Received Position 0, 0&h0D 0.
- Commands List:** Pos 010 Play, 011 Pause, 012 Still, 020 CueUp (selected), 021 CueUpTitle, 022 CueUpChapter, 023 CueUpTime, 024 CueUpTrack, 037 PlayToFramecode, 038 PlayToTime, 039 PlayToTitle, 040 PlayToChapter.
- Event List:** Search: ID 0 Device Global Variable T, 1 V7300\_1 P, 2 V7300\_2 P, 3 V7300\_3 P, 4 V7300\_4 P, 5 V7300\_5 P, 6 V7300\_6 P, 7 V7300\_7 P, 8 V7300\_8 P, 9 HSW Dreh scheiben ... S, 10 ioLogik E1214 C, 11 Remote Screen Rece... E, 12 V7300\_2 P, 13 System\_v4\_1216 C, 14 RemoteScreenRec C.
- Cuelists Table:**

Cuelists	ID	Device	Channels	Command	Parameter
Start_1	0	PJLink		SetInputVideo	
Start_2	1	V7300_1	v7300_1	CueUp	
Start_3	2				
Start_4					
Start_5					
Start_6					
Start_7					
Start_8					
Start_All					
Test Relais					
TestVP					
SendPos2					
MyBrandNewTask					

Finally we need a Play command

The screenshot shows the software interface with the following components:

- Devices:** HSW\_Dreh scheiben\_Mon, PJLink, ioLogik E1214, HSW Dreh scheiben Monit..., V7300\_1 (selected), V7300\_2, V7300\_3, V7300\_4, V7300\_5, V7300\_6, V7300\_7, V7300\_8, RemoteScreenRec, RemoteScreenSender, System\_v4\_1216.
- Var Name / Value:** Received Position 0, 0&h0D 0.
- Commands List:** Pos 010 Play (selected), 011 Pause, 012 Still, 020 CueUp, 021 CueUpTitle, 022 CueUpChapter, 023 CueUpTime, 024 CueUpTrack, 037 PlayToFramecode, 038 PlayToTime, 039 PlayToTitle, 040 PlayToChapter.
- Event List:** Search: ID 0 Device Global Variable T, 1 V7300\_1 P, 2 V7300\_2 P, 3 V7300\_3 P, 4 V7300\_4 P, 5 V7300\_5 P, 6 V7300\_6 P, 7 V7300\_7 P, 8 V7300\_8 P, 9 HSW Dreh scheiben ... S, 10 ioLogik E1214 C, 11 Remote Screen Rece... E, 12 V7300\_2 P, 13 System\_v4\_1216 C, 14 RemoteScreenRec C.
- Cuelists Table:**

Cuelists	ID	Device	Channels	Command	Parameter
Start_1	0	PJLink	pjlink	SetInputVideo	
Start_2	1	V7300_1	v7300_1	CueUp	
Start_3	2	V7300_1	v7300_1	Play	
Start_4	3				
Start_5					
Start_6					
Start_7					
Start_8					
Start_All					
Test Relais					
TestVP					
SendPos2					
MyBrandNewTask					

Now the task is finished. The projector switches to a video input, and the player starts playing from the beginning.

To start this task switch to *Run* mode, select the task and click the *Run Task* button.

## Send commands Synchronous to more then one Device

This is only possible if all the involved devices use the same driver. If you have a couple of players, all from the same type, then you can select some or all of

them in the *Device List*. The Command that is send to the Players is generated by the last selected device.

The screenshot shows the software interface with the 'Device List' on the left, the 'Event List' on the right, and a central 'Commands' panel. The 'Device List' shows a list of devices, with 'V7300\_1' through 'V7300\_8' selected. The 'Event List' shows a list of events, with 'V7300\_1' through 'V7300\_8' selected. The 'Commands' panel shows a list of commands, with 'Play' selected. The 'Event List' table is as follows:

ID	Device	Var Name	Value
0	Global Variable	Test	/
1	V7300_1	Position	/
2	V7300_2	Position	/
3	V7300_3	Position	/
4	V7300_4	Position	/
5	V7300_5	Position	/
6	V7300_6	Position	/
7	V7300_7	Position	/
8	V7300_8	Position	/
9	HSW Drehscheiben ...	Speed1	/
10	ioLogik E1214	D0Status	C
11	Remote Screen Rece...	D003	/
12	V7300_2	Position	C
13	System_v4_1216	CurrentTime	C
14	RemoteScreenRec	D001	/

The 'Event List' table is as follows:

ID	Device	Channels	Command	Parameter
0	V7300_8	v7300_1,v7300_2,v7300_3,v7300_4,v7300_5...	CueUp	"500"
1	V7300_8	v7300_1,v7300_2,v7300_3,v7300_4,v7300_5...	Play	
2	V7300_8	v7300_1,v7300_2,v7300_3,v7300_4,v7300_5...	Delay	100
3	V7300_8	v7300_1,v7300_2,v7300_3,v7300_4,v7300_5...	WaitForVariable	V7300_1.Position < 600
4	V7300_8	v7300_1,v7300_2,v7300_3,v7300_4,v7300_5...	Pause	

Notice that the Channel Parameter in the Cuelist now has all the channels of the involved devices. So the command string is generated by V7300\_8, but send to all selected devices.

## Edit a Cue

To edit a Cue, double click on it. If the Cue contains a control command for a device, the "Add Cmd" button changes to "Update". You can now modify the command and press the "Update" button"

## Non Device Commands


In the example above we saw how to add commands to a cuelist that concerns devices. But with only that, a cuelist is to limited. If you right-click into the cue list, you will get a context menu with further commands.

The screenshot shows a context menu for a cue. The menu options are:

- Insert >
- Edit >
- Wait For Variable
- Call as Function...
- Call as Thread...
- Stop Task...
- Stop All Tasks
- Delay...
- Repeat...
- Show Message...
- Comment...
- Shell Execute as Function...
- Shell Execute as Thread...

## Wait For Variable

One option to control a cuelists flow is the WaitForVariable command. If inserted, a window pops up to select the variable to wait for.



Let's complete the example above with the "MyBrandNewTask" cuelist. Remember that we send the player a CueUp command and a Play command. What's missing is a condition to stop playback and switch back the projectors input to another source.

In the *Search* field type the device name (V7300\_1). now only variables are shown that belong to this device. Select the variable *Position*. Next we need a condition how long to wait for this variable.

At the bottom of the window there is the selected variable (V7300\_1.Position in this case) and a drop down box with comparing parameters.

- < : Wait while less the value right
- > : Wait while more the value right
- <= : Wait while less or equal the value right
- >= : Wait while bigger or equal the value right
- <> : Wait while not equal the value right
- = : Wait while equal the value right

V4 Untitled

Search: v7300\_1

Device	Variable
V7300_1	Received
V7300_1	Position


V7300\_1.Position < 500

Cancel OK

enter a value in the field right and click OK

ID	Device	Channels	Command	Parameter
0	PJLink	pjlink	SetInputVideo	
1	V7300_1	v7300_1	CueUp	
2	V7300_1	v7300_1	Play	
3			WaitForVariable	V7300_1.Position < 500
4				

If *Show WaitForVariable Countdowns* is set in the Options->System dialog, the a Countdown window appears showing how long the cue will wait.




Now let's complete the task and stop the player and switch the input of the projector.

ID	Device	Channels	Command	Parameter
0	PJLink	pjlink	SetInputVideo	1
1	V7300_1	v7300_1	CueUp	0
2	V7300_1	v7300_1	Play	
3			WaitForVariable	V7300_1.Position < 500
4	V7300_1	v7300_1	Pause	
5	PJLink	pjlink	SetInputDigital	2
6				

## Repeat

The Repeat command is used to build loops. The instructions between Repeat and EndRepeat are looped as many times as entered. The Repeat command is available via Cuelist context menu (right click -> *Insert -> Repeat*) or main menu (*Insert -> Repeat*). A dialog box asks for the number of repeats. To create endless loops, enter 0 as value.





Next, fill the part between Repeat and Endrepeat with instructions. It is possible to move the Repeat or EndRepeat command via Cut (*Ctrl+X*) and Paste (*Ctrl+V*).


In the example below we created an endless loop that plays a video from position 0 to position 500. The *Delay* between the *Play* command and the *WaitForVariable* command is necessary for the following reason: The player receives the two commands CueUp and Play. During this sequence, the device driver can not ask for the position, because the player is busy with the two commands. That means that the device variable *Position* still has the last value (500 or more). In that case the WaitForVariable Condition is true and the cue is skipped. One solution to avoid this is to set a small Delay, so the driver has time to update the correct position. Another solution is to modify the driver. With the CueUp command we can set the Device Variable position to the value of the CueUp command. In this case we don't need the delay.

The loop sequence now looks like this:

ID	Device	Channels	Command	Parameter
0			Repeat	0
1	V7300_1	v7300_1	CueUp	
2	V7300_1	v7300_1	Play	
3			Delay	100
4			WaitForVariable	V7300_1.Position < 500
5	V7300_1	v7300_1	Pause	
6			EndRepeat	
7				

## Delay


It might be necessary to have a Delay between two commands to pause the task for a given amount of time (see example above). In the main menu select *Insert -> Delay* or use the context menu. The Delay is specified by the value in milliseconds.



Delays displayed with a violet background in the list.

## Call as Function

Even in complex projects it makes sense to split the whole project into several subroutines. This makes maintenance easier and gives a better overview over the projects structure. Every Task, whether a Cuelist or Script, can be a function. If a task is executed, it is usually processed from top to bottom. A *CallAsFunction* branches to the task specified, finishes the called task and returns to the next command in the calling task.



To call a task as function, select *Insert -> CallAsFunction* in main menu or Cuelist context menu (right click *Insert -> CallAsFunction*). That opens the Task Selector presenting all tasks (Cuelists and Scripts). Choose the task that has to be called.

Select Cueset

Search:

Toggle\_Test  
HandleChanged  
t1  
t2  
t3  
t4  
t5  
t6  
t7  
t8  
tall  
SendSpeed  
ToggleD003  
InDI\_Moxa  
SendTime  
SendPosition  
ResetD001  
Reset003  
SetProgress  
Start1


Cancel
Add

Finally, the new CallAsFunction command in's inserted in the Cuelist.

ID	Device	Channels	Command	Parameter
0			CallAsFunction	SetProjectorInput
1			Repeat	0
2	V7300_1	v7300_1	CueUp	
3	V7300_1	v7300_1	Play	
4			Delay	100
5			WaitForVariable	V7300_1.Position < 500
6	V7300_1	v7300_1	Pause	
7			EndRepeat	
8				

## Call as Thread

In contrast to CallAsFunction, a CallAsThread instruction launches the new task parallel to the calling task. The calling task is not paused during the time, the called task is executed. The programmer / operator has to take care that the two parallel running tasks don't use the same resources (devices / channels).




To create a CallAsThread instruction select *Insert -> CallAsThread* in main menu or use the Cuelists context menu (right click *Insert -> CallAsThread*). That opens the Task Selector presenting all tasks (Cuelists and Scripts). Choose the task that has to be called.

## Stop Task

It might be necessary to stop a running task before it terminates regularly. This can be done manually via *Stop Task* tool button or as instruction from a running task. Assuming there is an endless loop working with two Players. Now the Players needed for some other action, but it is impossible to use them as long as the endless loop is running. With the StopTask command it is possible to terminate the endless loop and then use the Players in another task.

The command is available via main menu *Insert -> Stop Task* or the Cuelists context menu. That opens the Task Selector presenting all tasks (Cuelists and Scripts). Choose the task that has to be stopped.




## Stop All Tasks

same as StopTask, but stops all tasks except the one that is calling this command.

## Show Message

The ShowMessage command is used to display a message in the status bar. Via main menu *Insert -> Show Message* or Cuelist context menu this command is available.




If the instruction is executed, the message appears in the status bar.

ID	Device	Channels	Command	Parameter
0			ShowMessage	An endless loop is running
1			CallAsFunction	SetProjectorInput
2			Repeat	0
3	V7300_1	v7300_1	CueUp	00 00 00 00 00 00
4	V7300_1	v7300_1	Play	00 00 00 00 00 00
5			Delay	100
6			WaitForVariable	V7300_1.Position < 500
7	V7300_1	v7300_1	Pause	00 00 00 00 00 00
8			EndRepeat	00 00 00 00 00 00
9				

An endless loop is running

## Comment

*Insert -> Comment* allows to insert a comment to the list. A comment is only for documentation purpose and should describe what happens in this part of the Cuelist.



A comment appears in the Cuelist with a dark red background.

ID	Device	Channels	Command	Parameter
0			ShowMessage	An endless loop is running
1			Comment	Switch the Projector to Video 1
2			CallAsFunction	SetProjectorInput
3			Repeat	0
4	V7300_1	v7300_1	CueUp	0
5	V7300_1	v7300_1	Play	
6			Delay	100
7			WaitForVariable	V7300_1.Position < 500
8	V7300_1	v7300_1	Pause	
9			EndRepeat	
10				

An endless loop is running

A comment has no functionality for the script. During task execution it is ignored. The only purpose is to make notes for the user to have a documentation for the script.

## Shell Execute as Function

The ShellExecuteAsFunction command is used to launch shell commands / scripts. It works similar to CallAsFunction, and is available via main menu *Insert -> Shell Execute As Function* or the cuelist context menu.

A dialog asks for the shell command and optional parameters:

ShellExecute commands are displayed with red background in the cuelist.

In this example notepad.exe is called. If programs or scrips needs to be executed that are not in the operating systems path variable, the the complete path must be given here.

Cuelists	ID	Device	Channels	Command	Parameter
Start_3	0			ShellExecuteAsFunction	notepad.exe
Start_4	1				
Start_5					
Start_6					
Start_7					
Start_8					
Start_All					
Test Relais					
TestVP					
SendPos2					
MyBrandNewTask					
SetProjectorInput					
StartNotepad					

## Shell Execute as Thread


**ShellExecuteAsThread** launches programs / scripts as thread ( see **Shell Execute as Function**). V-Control launch the shell command and returns immediately, without waiting for the shell command to finish.

# Scripts


These kind of tasks are much more powerful than Cuelists. Scripts offer access to the integrated Basic language. The modern compiler compiles native code for every supported platform. V-Control Basic enhances the standard Basic by commands giving access to the Device Driver and Tasks as well as to globally shared variables. In the Compiler section, there is a list of all available commands and functions.

## Create Scripts


To create a Script switch to Script View.



Then select *Tasks* -> *Add* in main menu or via Cueset list context menu (right click) select Add Task. Alternatively the click the *Add Task* tool button.



Now the task has to be filled with instructions. Generally this is the same procedure than programming Cuelists. In the following example we send an OSC (Open Sound Control) message to a device. Select the device in the *Device List*, select the command in the *Command List* and enter the parameter. Then click the *Add Cmd* button.



The command generated has this structure:


```
RunCmd("Device Name","Channel Name","Command Name","Device
Parameter 1","Device Parameter 2",
"Command Parameter 1","Command Parameter 2","Command Parameter
3","Command Parameter 4")
```

Parameters that are empty shown as ""

So the resulting entry is

```
RunCmd("OSC_1220","osc","SimpleOSCInteger","/
test","","123123","","","")
```

Next step is to modify this command. Assume that the *SimpleOSCInteger* command controls a fader value, and the fader should move from 0 to 100 in 2 seconds. The script can be something like this:





**Dim v as Variant** creates a local variable v. The type Variant is very flexible. It behaves as an integer if used so. But the content of the variable is converted to string if a string is needed. The **For** loop accepts only Integers as loop iterator, but the **RunCmd** Function accepts only string parameters. In both cases we can use a variant variable.

Here is an example with Integer and String Variables:

```
Dim i as Integer
Dim s as String

for i = 0 to 100
    s = str(i)

RunCmd("OSC_1220","osc","SimpleOSCInteger","/test","",s,"","","")
    Delay("20")
Next
```

The **str** Function converts an Integer to String

## IOResult

Every RunCmd instruction changes the variable IOResult. IOResult does not have to be declared, it is a (string) variable that is part of every Script and contains the result of the last RunCmd instruction.


```
dim i as integer

RunCmd("C-Control IO Box","ccontrol","Get_ADC_1","", "", "", "", "", "")
i = val(IOResult)
if i > 25 then CallAsFunction("TurnOnAirCo")
```

In the example above a Get\_ADC\_1 command is sent to a C-Control I/O interface. The result of the command is stored in the variable IOResult. The value of IOResult is (in this case) the measured value of analog digital converter (ADC) 1 of the C-Control interface. Because the type of IOResult is string, but the value is needed (for comparison) as integer, the line `i = Val(IOResult)` converts the string to an integer. If the measured value is bigger than 25, an air condition is switched on.


## Delay

It might be necessary to have a Delay between two commands to pause the task for a given amount of time. In the main menu select *Insert -> Delay* or use the context menu. The Delay is specified by the value in milliseconds.




## Call As Function

Even in complex projects it makes sense to split the whole project into several subroutines. This makes maintenance easier and gives a better overview over the projects structure. Every Task, whether a Cuelist or Script, can be a function. If a task is executed, it is usually processed from top to bottom. A *CallAsFunction* branches to the task specified, finishes the called task and returns to the next command in the calling task.




To call a task as function, select *Insert -> CallAsFunction* in main menu or Script Editor context menu (right click *Insert -> CallAsFunction*). That opens the Task Selector presenting all tasks (Cuelists and Scripts). Choose the task that has to be called.




## Call As Thread

In contrast to `CallAsFunction`, a `CallAsThread` instruction launches the new task parallel to the calling task. The calling task is not paused during the time, the called task is executed. The programmer / operator has to take care that the two parallel running tasks don't use the same resources (devices / channels).




To create a `CallAsThread` instruction select *Insert -> CallAsThread* in main menu or use the Script Editor's context menu (right click *Insert -> CallAsThread*). That opens the Task Selector presenting all tasks (Cuelists and Scripts). Choose the task that has to be called.



## Stop Task

It might be necessary to stop a running task before it terminates regularly. This can be done manually via Icon / Toolbar) or as instruction from a running task. Assuming there is an endless loop working with two DVD Players. Now the DVD Player are needed for some other action, but it is impossible to use them as long as the endless loop is running, because they are blocked. With the StopTask command it is possible to terminate the endless loop and then use the DVD Players in another task.

The command is available via main menu *Insert -> Stop Task* or the Script Editor's context menu. That opens the Task Selector presenting all tasks (Cuelists and Scripts). Choose the task that has to be stopped.



## Show Message

The ShowMessage command is used to display a message in the status bar. Via main menu *Insert -> Show Message* or Script Editor's context menu this command is available.

## Local Variables

Local variables are only available in the task where they have been declared. While declaring a variable, its type is set. The following types are available:


- Integer (32 Bit)
- Single (16 Bit integer)
- Double (64 Bit Floating Point)
- Boolean (True or False)
- String (e.g. "Hello World")
- Variant (any)

It is possible to build arrays from all those types.

A variable is declared by the Dim statement. Variable names must start with a letter and must not contain special characters. Here some examples:


- Dim A1 As Integer correct
- Dim Ä1 As Integer incorrect
- Dim 1A As Integer incorrect

- Dim A 1 As Integer incorrect, space not allowed
- Dim A\_1 As Integer correct



In the screenshot above, the Dim statement declares a String variable named foo. Then, the variable foo gets the value "Hallo Welt". The content of foo is displayed by the ShowMessage command with foo as parameter. In this example, a line ShowMessage("Hallo Welt") would have the same result.

Variant variables are very special. Because they have no (or any) type, they are very flexible. A variant stores a value in different formats and "knows" which one is needed if there is an access to. In the example below a variant variable named v is declared:



In the For . . Next loop, an integer value is assigned to v. As discussed above, the ShowMessage command need a string variable as parameter, but the line ShowMessage("Count:" + v) is working correct, because v knows that only strings are valid and present its content as string. So v is used as integer and as string in the same subroutine. A more structured solution for the same job is the example below:

```
dim i as integer
for i = 1 to 10
    ShowMessage("Count:" + str(i))
    Delay("1000")
next
|
Line:8
```

---

```
Count:10
```

At first, an integer variable *i* is declared. The beginning of the For . .Next loop is unchanged, because the For..Next instruction expect an integer variable anyway. The command `ShowMessage("Count:" + i)` will not work, because it is impossible to add an integer to a string. But V-Control Basic knows a function that converts an integer to string, the `Str(i)` command. The result of `str(i)` is "10", if *i* has the value 10. The string "10" comprising from ASCII code 49 ("1") and ASCII code 48 ("0").

An Overview of available basic functions is available in the Basic Language Reference Chapter.

Another often used variable type is boolean. Boolean variables know to states, True or False (1/0).

```
dim b1 as boolean
b1 = PromptMessage("Click Yes or No")
if b1 = True then
    ShowMessage("Yes was pressed")
else
    ShowMessage("No|was pressed")
end
Line:7
```


---

```
No was pressed
```


In this example, the variable *b1* is declared as Boolean. The `PromptMessage` command need a boolean variable to return the result of the `PromptMessage` dialog. If the result is True, the OK button was pressed, if False, the user clicked the Cancel button. The `if..then` instruction check *b1* and branch to the correct `ShowMessage` command.

## Global Variables


Global variables are accessible from every Script. It is possible e.g. to assign a global variable a value in task A, and check this value in task B. Global variables are from type string only. Because every Script has access to global variables, it is not declared in a Script. To declare a global variable, select *Cues -> Add Global Variable...* in the main menu or use the context menu of the Global Variables list.



Enter the name of the variable in the dialog box:




The new variable appears in the Global Variables list. At this point, the content of the new variable is an empty string "".




To access the global variables, the commands *GetGlobalVar* and *SetGlobalVar* are used (available via main menu *Insert -> GetGlobalVar*, *Insert -> SetGlobalVar* or the Script Editor's context menu).





To assign a value to a global var, use the function *SetGlobalVar*. As shown in the picture above, it is available via Script Editor's context menu. In the following dialog (see below) select a variable from the list and enter a value for that variable:



The result is `SetGlobalVar("MyVariable", "Hello")`


If this task is launched, the variable `MyVariable` gets the string "Hello" as content. To check this, run the task.

To read a global variable use *GetGlobalVar*. Instructions like `"MyVariable" = "6"` are invalid, because `"MyVariable"` is a string and not a variable. `MyVariable = "6"` is also invalid, because `MyVariable` is not declared in the Script and only (locally) declared variables are known. The solution is to declare a local variable of type string and assign the content of the global variable to that local one.


```
Dim MyLocalVar as string
```

Via main menu *Insert -> GetGlobalVar*, or the Script Editor's context menu a dialogue box with all available global variables pops up. If a variable is selected

a new dialogue box asks for the local variable, that gets the content of the global one.



The result looks like this:




now, the content of the global variable is available in the Script and we can work with it.

## Shell Execute As Function

The ShellExecuteAsFunction command is used to launch shell commands / scripts. It works similar to CallAsFunction, and is available via main menu *Insert* -> *Shell Execute As Function* or the context menu.

A dialogue asks for the shell command and optional parameters:



## **Shell Execute As Thread**

ShellExecuteAsThread launches programs / scripts as thread ( Shell Execute as Function). V-Control launch the shell command and returns immediately, without waiting for the shell command to finish.

# Compiler

## Basic Language Reference

---

### Abs

Abs (Double) As Double

Returns the absolute value of the number specified.

Dim d As Double

```
d=Abs(23.9) //returns 23.9  
d=Abs(-23.9) //returns 23.9
```

---

### Acos

Acos (Double) As Double

Returns the arccosine of the value specified. The arccosine is the angle whose cosine is value. The returned angle is given in radians.

Dim d As Double

```
Const PI=3.14159265358979323846264338327950  
d=Acos(.5) //returns 1.0471976  
d=Acos(.5)*180/PI //returns 60
```

---

### Asc

Asc (String) As Integer

Returns as an Integer, the ASCII value for the first character of a String.

Dim a As Integer

```
a = Asc("@") //returns 64
```

The Asc function returns the code point for the first character in the String passed. Characters 0 through 127 are the standard ASCII set. They will be the same on practically every platform. Asc returns the code point for whatever encoding the string is in. If the string is in MacRoman, you get the code point specified by MacRoman, and so forth.

If you need to get the ASCII code of the first byte of the string rather than the first character, use the AscB function.

---

## AscB

AscB (String) As Integer

Returns as an Integer, the value for the first byte of a String.

```
MsgBox Str(AscB("a")) //returns 97
```

```
MsgBox Str(AscB("A")) //returns 65
```

The AscB function returns the code for the first byte in the String passed. If you need to get the character code of the first character of the string rather than the first byte, use the Asc function.

AscB should be used instead of Asc when the string represents binary data or when your application will run on a one-byte character set (such as the US system) and you want case-sensitivity.

---

## Asin

Asin (Double) As Double

Returns the arcsine of the value specified.

```
Dim d as Double
```

```
Const PI=3.14159265358979323846264338327950
```

```
d=Asin(.5) //returns 0.5235988
```

```
d=Asin(.5)*180/PI //returns 30
```

The arcsine is the angle whose sine is value. The Asin function returns the angle (in radians) of the sine passed to it. To express the arcsine in degrees, multiply the result by 180/PI.

---

## Atan

Atan (Double) As Double

Returns the arctangent of the value specified. The arctangent is the angle whose tangent is value.

```
Dim d as Double
```

```
Const PI=3.14159265358979323846264338327950
```

```
d=Atan(1) //returns 0.785398 (PI/4 radians)
```

```
d=Atan(1)*180/PI // returns 45
```

---

## Atan2

Atan2 (Double, Double) As Double

Returns the arctangent of the point whose coordinates are x and y. The

arctangent is the angle from the x-axis to a line drawn through the origin (0,0) and a point with coordinates x, y.

```
Dim d as Double
```

```
Const PI=3.14159265358979323846264338327950
```

```
d=Atan2(1,0) //returns 1.57
```

```
d=Atan2(1,0)*180/PI //returns 90
```

---

## BitAnd

The BitAnd method returns a UInt64 that is the result of comparing each bit of the two integers passed and assigning 1 to the bit position in the integer returned if both bits in the same position in the integer passed are 1. Otherwise, 0 is assigned to the bit position.

```
Dim i As Integer
```

```
i = BitAnd(5, 3) // returns 1
```

---

## BitOr

The BitOr method returns a UInt64 that is the result of comparing each bit of the two integers passed and assigning 1 to the bit position in the integer returned if either of the bits in the same position in the integers passed are 1. Otherwise, 0 is assigned to the bit position.

```
Dim i As Integer
```

```
i = BitOr(5, 3) // returns 7
```

---

## BitXor

The BitXor method returns a UInt64 that is the result of comparing each bit of the two integers passed and assigning 1 to the bit position in the integer returned if both bits in the same position in the integers passed are not equal. Otherwise, 0 is assigned to the bit position.

```
Dim i As Integer
```

```
i = BitXor(5, 3) // returns 6
```

---

## BCDToTCString

Timecode from Devices with Sony 9-pin protocol and compatible usually comes in BCD format (4 Bytes FFSSMMHH). This function converts it to a string (HH-MM-SS-FF)

```
dim sTC, sBCD as string
```

```
//assign value to sBCD
```

```
//by reading the value from a device  
sTC = BCDToTCString(sBCD)
```

---

## **Ceil**

Ceil (Double) As Double

Returns the value specified rounded up to the nearest Integer.

Dim d as Double

```
d=Ceil(1.234) //returns 2
```

---

## **ChangeCMD\_MinMax**

This Command is available only in Device Drivers. It is used to update a drop down list with parameter values.

```
ChangeCMD_MinMax("CueSpot", "P1", res)
```

See Device Editor Automatic Parameters for more information.

## **Checksum8Bit**

Checksum8Bit(string) As Integer

Returns the Check-sum of a string. Each byte of the string is treated as binary value (not as ASCII code) and is added to the Check-sum. If the Check-sum exceed 256 in "roll over" to zero.

Dim c as integer

```
c = CheckSum8Bit("ABC")    // returns 198
```

```
c = CheckSum8Bit(chr(1)+chr(2)+chr(3)) // returns 6
```

---

## **ChecksumMod255**

ChecksumMod255(string) As Integer

Returns the Check-sum of a string. Each byte of the string is treated as binary value (not as ASCII code) and is added to the Check-sum. The result is the Sum Mod 255.

---

## **checksumXOR**

Returns the XOR Checksum of a given string

dim sXor as string

```
sXour = checksumXOR("My String to Checksum")
```

---

## CRC16

Returns the CRC16 Checksum of a given string

```
dim sCrc as string  
sCrc = CRC16("My String to Checksum")
```

---

## Chr

Chr (Double) As String

Returns the character whose ASCII value is passed.

```
Dim Tab,CR,MyA as String
```

```
Tab=Chr(9) //returns a tab  
CR=Chr(13) //returns carriage return  
MyA = Chr(65) //returns "A"
```

**The Chr function will return a single byte String when running on single byte systems and return a double byte string when running on double byte systems. If you need to get a single byte string regardless of whether the system software is single or double byte, use the ChrB function.**

---

## ChrB

ChrB (Double) As String

Returns a single byte String whose value is passed.

```
Dim s as String
```

```
s=ChrB(32) //returns a space  
s=ChrB(13) //returns carriage return
```

The ChrB function returns a single byte string whose value is specified. ChrB should be used rather than Chr when value represents binary data.

If you need to get a single byte string when running on single byte system software and a double byte string when running on double byte system software, use the Chr function.

If you need to specify a code point above 127, use the Chr property of the TextEncoding class. With it, you specify both the encoding and the character code in that encoding.

---



## Const

Const name = value

Declares a value as a local constant.

```
Const Pi=3.14159265358979323846264338327950
```

The Const statement can be used in place of the Dim statement followed by an assignment statement when you are sure that the value of the variable should not change within the method. Using Const instead of Dim provides a convenient way to manage such values.

A Const statement can be placed anywhere in a method, including inside a conditional structure, such as an If statement, or a looping structure. Constants declared in this manner are local to the method.

---

## Cos

Cos (Double) As Double

Returns the cosine of the given angle.

```
Dim d as Double
```

```
Const PI=3.14159
```

```
d=Cos(45*PI/180) //returns 0.707
```

---

## CountFields

CountFields (String, String) As Integer

Returns the number of values (fields) in the string passed that are separated by the separator string passed. If the source string is binary data or you require case-sensitivity, use CountFieldsB instead.

The example below returns 5.

```
Dim count as Integer
```

```
Dim s as String
```

```
s="Dan*Smith*11/22/69*5125554323*Male"
```

```
count=CountFields(s, "*")
```

The following example returns three because it counts the null "field" after the (unnecessary) final field delimiter.

```
Dim count as Integer
```

```
Dim s as String
```

```
s="Dan*Smith*"
```

```
count=CountFields(s, "*")
```

## CRC16

Returns a CRC16 calculated checksum

---

## Delay

Delay (String)

Waits the given number in ms. The given number must be a string.

```
Delay("1000")    //Wait 1 Second
```

```
Dim i as integer
```

```
i = 500
```

```
Delay(str(i))    //Wait 500 ms
```

---

## Exit

Exit

The Exit statement causes control to exit a loop and jump to another line of code without the loop conditions being satisfied. The optional keywords enable you to control where execution will resume.

- If you use Exit without any optional keywords, V-Control exits whatever loop the Exit statement is in.
- If you use Exit with the Do keyword, V-Control exits the Do loop it is in, even if it is also inside another type of loop.
- If you use Exit with the While keyword, V-Control exits the While loop it is in, even if it is also inside another type of loop.
- If you use Exit with the For keyword without passing a parameter, it exits the innermost For loop it is in, even if it is also inside another loop.
- If you have nested For statements, you can pass the For keyword the variable that controls the loop you want to exit. For example, if you are testing all the elements of a two-dimensional array with nested For statements, you can use the loop variable for the outermost loop to exit at that point.

```
For i= 0 to 255
  For j= 0 to 255

    If myArray(i,j) = 23 then
      Exit For i
    End if
  Next
Next
Next
```

---

## Exp

Exp( Double) As Double

Returns “e” to the power of the value specified.

Dim d as Double

d=Exp(10) //returns 22026.4657948

---

## FloatStringToStr

Converts a string representing a double i.e. “1.204”) to a four byte float string

**This is the code behind the function call**

Sub FloatStringToStr(fString as string) As String

//converts a string representing a float value ("1.2302") to a four byte float string

Dim mb As MemoryBlock = New MemoryBlock(4)

dim s, stmp as string

dim FloatVal as Single

FloatVal = CDBl(fString)

mb.SingleValue(0) = FloatVal

// automatic conversion between memoryblock and strings!! =)

s = mb

stmp = mid(s,4,1)+mid(s,3,1)+mid(s,2,1)+mid(s,1,1)

return stmp

End Sub

---

## Floor

Floor( Double) As Double

Returns the value specified rounded down to the nearest Integer.

Dim d as Double

d=Floor(1.234) //returns 1

## For...Next

For...Next

Executes a series of statements a specified number of times. The For Each... Next statement is a variation that executes once for each element of a one-dimensional array.

The counter variable in a For statement can be declared inside the For

statement rather than externally, as a local variable. For example, the code:

```
Dim i as Integer

For i=0 to 10
    //your code goes here
Next
```

The following example uses the DownTo keyword to decrement the counter:

```
Dim i as Integer

For i=5 DownTo 1 Step 1
    Beep
Next
```

---

## Format

Format (Double, String) As String

Returns as a String a formatted version of the number passed based on the parameters specified. The Format function is similar to the way spreadsheet applications format numbers. Format will use the information based on the user's locale even if the user's locale is a Unicode-only locale.

Syntax

result = Format( number, formatSpec )

The formatSpec is a string made up of one or more special characters that control how the number will be formatted:

Character	Description
#	Placeholder that displays the digit from the value if it is present.If fewer placeholder characters are used than in the passed number, then the result is rounded.
0	Placeholder that displays the digit from the value if it is present.If no digit is present, 0 (zero) is displayed in its place.
.	Placeholder for the position of the decimal point.
,	Placeholder that indicates that the number should be formatted with thousands separators.
%	Displays the number multiplied by 100.
(	Displays an open paren.
)	Displays a closing paren.

+	Displays the plus sign to the left of the number if the number is positive or a minus sign if the number is negative.
-	Displays a minus sign to the left of the number if the number is negative. There is no effect for positive numbers.
E or e	Displays the number in scientific notation.
\character	Displays the character that follows the backslash.

The absolute value of the number is displayed. You must use the + or - signs if you want the sign displayed.

Although the special formatting characters are U.S. characters, the actual characters that will appear are based on the current operating system settings. For example, Windows uses the settings in the user's Regional and Language Options Control Panel. Formatting characters are specified in similar ways on other operating systems.

The formatSpec can be made up of up to three formats separated by semicolons. The first format is the format to be used for positive numbers. The second format is the format to be used for negative numbers and the third format is the format to be used for zero.

The following are several examples that use the various special formatting characters.

<b>Format</b>	<b>Number</b>	<b>Formatted String</b>
#.##	1.786	1.79
#.0000	1.3	1.3000
0000	5	0005
#%	0.25	25%
###,###.##	145678.5	145,678.5
###e	145678.5	1.46e+5
-###	-3.7	-3.7
+###	3.7	+3.7
###;(###);z\er\o	3.7	3.7
###;(###);z\er\o	-3.7	(3.7)
###;(###);z\er\o		zero

The following example returns the number 3560.3 formatted as \$3,560.30.

```
Dim s as String
```

```
s=Format(3560.3, "$###,##0.00")
```

## FramecodeToTimecode

returns a string that contains a Timecode in the format “hh-mm-ss-ff”. The function uses the Global Framerate (Main Menu -> Options) to determine the frames per second. The following example converts a framecode to a timecode.

```
dim tc as string  
tc = FramecodeToTimecode(123456)
```

---

## GetDayOfMonth

Returns the day of the current month (1..31)

Result integer

---

## GetDayOfWeek

Result integer (Sunday=0, Monday = 1...)

---

## GetDeviceVar

Gets the string value of a device variable.

**In a Device Driver, the syntax is**

```
dim s as string  
s = GetDeviceVar("VariableName")
```

**In a Task, the syntax is**

```
dim s as string  
s = GetDeviceVar("DeviceName","VariableName")
```

All Parameters are strings

---

## GetGlobalVar

Gets the String Value of a Global variable

```
Dim s as String  
s = GetGlobalVar("Test")
```

This Function call is not available in Device Drivers.

---

## GetHour

Result integer

---

## GetMinute

Result integer

---

## GetMonth

Result integer

---

## GetTime

Result string

This function returns a Timecode Time string. The format is HH:MM:SS:FF (FF = Frames). To determine the Timecode format, the function need a parameter for the framerate (fps)

```
Dim res as string  
dim framerate as integer
```

```
framerate = 25  
res = GetTime(framerate)
```

---

## GetSeconds

Result integer

---

## GetYear

Result integer

---

## Hex

Hex (Integer) As String

Returns as a String the hexadecimal version of the number passed.

If the value is not a whole number, the decimal value will be truncated.

You can specify binary, hex, or octal numbers by preceding the number with the & symbol and the letter that indicates the number base. The letter b indicates binary, h indicates hex, and o indicates octal.

```
Dim hexVersion As String
```

```
hexVersion=Hex(5) //returns "5"  
hexVersion=Hex(75) //returns "4B"
```

```
hexVersion=Hex(256) //returns "100"
```

---

## HexToStr

HexToStr (String) As String

Returns as a String hexadecimal numbers converted to string

dim s as string

```
s = HexToStr("414243")
    // Returns "ABC", because "A" has ASCII code &h41 or 65
    decimal,
    //           "B" has ASCII code &h42 or 66 decimal etc.
```

---

## If...Then...Else

If...Then...Else

Conditionally executes a group of statements, depending on the value of a Boolean expression.

When executing an If statement, the condition is tested. If condition is True, the statements associated with the If statement following the Then statement are executed. If condition is False and an Else clause follows, its statements will be executed. If condition is False and there is no Else clause or it is preceded by an Elself statement, the condition following the Elself statement is tested. After executing the statements following Then, Elself or Else execution continues with the statement that follows End If.

```
If error=-123 Then
    Beep
    MsgBox "Whoops! An error occurred."
End If
```

```
Dim theNumber As Integer
Dim digits As Integer
```

```
theNumber=33
If theNumber<10 Then
    digits=1
ElseIf theNumber<100 Then
    digits=2
ElseIf theNumber<1000 Then
    digits=3
Else
    digits=4
End If
```

---



## InStr

InStr (Integer, String, String) As Integer

Returns the position of the first occurrence of a String inside another String. The first character is numbered 1.

Dim first As Integer

```
first = InStr("This is a test", "t")      //returns 1
first = InStr("This is a test", "is")     //returns 3
first = InStr(4, "This is a test", "is") //returns 6
first = InStr("This is a test", "tester")//returns 0
```

---

## InStrB

InStrB (Integer, String, String) As Integer

If the find string is not found within the source string, 0 (zero) is returned. InStrB is case-sensitive; it treats source as a series of raw bytes. It should be used instead of InStr when the string represents binary data or when your application will run in a one-byte character set (such as the US system) and you want case-sensitivity.

Dim first As Integer

```
first = InStrB("This is a test", "T")     //returns 1
first = InStrB("This is a test", "t")     //returns 11
first = InStrB("This is a test", "is")    //returns 3
first = InStrB(4, "This is a test", "is") //returns 6
first = InStrB("This is a test", "tester")//returns 0
first = InStrB("This Is a test", "Is")    //returns 6
```

---

## Left

Left (String, Integer) As String

Returns the first n characters in a source String.

Dim s As String

```
s=Left("Hello World", 5) //returns "Hello"
s="Hello World"
s=s.Left(5) //returns "Hello"
```

---

## LeftB

LeftB (String, Integer) As String

Returns the first n bytes in a source String.

The LeftB function returns bytes from the source string starting from the left side (as the name implies). If you need to read characters rather than bytes, use the Left function.

This example uses the LeftB function to return the first 5 bytes from a string.

```
Dim s As String
s=LeftB("Hello World", 5) //returns "Hello"

s="Hello World"
s=s.LeftB(5) //returns "Hello"
```

---

## Len

Len (String) As Integer

Returns the number of characters in the specified String.

```
Dim n As Integer
n=Len("Hello world") //returns 11
```

```
Dim s as String
s="Hello World"
n=s.Len //returns 11
```

---

## LenB

LenB (String) As Integer

Returns the number of characters in the specified String.

LenB treats string as a series of bytes, rather than a series of characters. It should be used when string represents binary data. If you need to know the number of characters in string rather than the number of bytes, use the Len function.

---

## Log

Log (Double) As Double

Returns the natural logarithm of the value specified.

```
Dim d As Double
d=Log(10) //returns 2.3025851
```

---

## Lowercase

Lowercase (String) As String

Converts all characters in a String to lowercase characters.

```
Dim s As String
s=Lowercase("tHe Quick fOX") //returns "the quick fox"
s=Lowercase("THE 5 LAZY DOGS") //returns "the 5 lazy dogs"

s="tHe Quick fOX"
s=s.Lowercase /returns "the quick fox"
```

---

## LTrim

LTrim (String) As String

Returns the String passed with leading (left side) whitespaces removed.

```
Dim s as String
s=LTrim(" Hello World ")
//Returns "Hello World "
s=" Hello World "
s=s.LTrim //Returns "Hello World "
```

---

## Max

Max (Double, Double) As Double

Returns the largest value passed to it.

```
Dim d As Double

d=Max(3.01, 4.05) //returns 4.05
d=Max(3.012, 3.011, 1.56) //returns 3.012
```

---

## Microseconds

Microseconds As Double

Returns the number of microseconds (1,000,000th of a second) that have passed since the user's computer was started.

Dim minutes As Integer

```
minutes=Microseconds/1000000/60
MsgBox "Your computer has been on for "+ Str(minutes)+" minutes."
```

Because modern operating systems can stay running for so long, it's possible for the machine's internal counters to "roll over." This means that if you are using this function to determine how much time has elapsed, you may

encounter a case where this time is inaccurate.

---

## Mid

Mid (String, Integer, Integer) As String

Returns a portion of a String. The first character is numbered 1.

Dim s As String

```
s = Mid("This is a test", 6) //returns "is a test"
```

```
s = Mid("This is a test", 11, 4) //returns "test"
```

```
s="This is a test"
```

```
s=s.Mid(11,4) //returns "test"
```

---

## MidB

MidB (String, Integer, Integer) As String

Returns a portion of a String. The first character is numbered 1.

Dim s As String

```
s=MidB("This is a test", 6) //returns "is a test"
```

```
s=MidB("This is a test", 11, 4) //returns "test"
```

```
s="This is a test"
```

```
s=s.MidB(11,4) //returns "test"
```

MidB treats source as a series of bytes, rather than a series of characters. MidB should be used when source represents binary data. If you need to extract characters rather than bytes, use the Mid function. To determine the number of bytes in a String, use the LenB function.

---

## Min

Min (Double, Double) As Double

Returns the smallest of the numbers passed.

Dim d As Double

```
d=Min(3.01, 4.05) //returns 3.01
```

```
d=Min(3.012, 3.011) //returns 3.011
```

---

## msToTimecode

Convert Milliseconds to Timecode. Returns a string that contains a Timecode in the format "hh-mm-ss-ff". The function uses the Global Framerate (Main Menu - > Options) to determine the frames per second. The following example converts a framecode to a timecode.

```
dim tc as string  
tc = msToTimecode(1000) // tc = 00-00-01-00
```

---

## Nil

Nil

Used to determine if an object is nil (no value).

---

## NthField

NthField (String, String, Integer) As String

Returns a field from a row of data. The first field is numbered 1. If you need to parse binary data, use NthFieldB instead.

This example returns "Smith"

```
Dim field As String  
field=NthField("Dan*Smith*11/22/69*5125554323*Male","*",2)  
//Field = smith
```

In the example above, the \* is a field delimiter. The string "Dan\*Smith\*11/22/69\*5125554323\*Male" has 5 fields if \* is the delimiter.

1. "Dan"
2. "Smith"
3. "11/22/69"
4. "5125554323"
5. "Male"

If / is chosen as delimiter, then the string has 3 fields:

1. "Dan\*Smith\*11"
2. "22"
3. "69\*5125554323\*Male"

Result = NTHField(StringWithFields, Delimmiter, Position)

---

## NthFieldB

Returns a field from a row of data. NthFieldB is identical to NthField except that it treats the source data as binary data. The first field is numbered 1.

This example returns "Smith"

```
Dim field As String
field = NthFieldB("Dan*Smith*11/22/69*5125554323*Male", "*", 2)
```

Using the second syntax:

```
Dim s, field As String
s = "Dan*Smith*11/22/69*5125554323*Male"
field = s.NthFieldB("*", 2)
```

---

## Oct

Oct (Integer) As String

Returns as a String, the octal version of the number passed.

Dim OctVersion As String

```
OctVersion=Oct(5) //returns "5"
OctVersion=Oct(75) //returns "113"
OctVersion=Oct(256) //returns "400"
```

---

## Pow

Pow (Double, Double) As Double

Returns the value specified raised to the power specified.

This example uses the Pow function to return four raised to the power of seven.

```
Dim d As Double
d=Pow(4,7) //returns 16384
```

---

## Redim

Redim Array(x,y)

Resizes the passed array.

This example reduces the aNames array to 11 elements.

```
Redim aNames(10)
```

This example adds 10 elements to the aNames array

```
Redim aNames( Ubound(aNames)+10)
```

This example reduces the aPeople array to 11 elements for the first dimension

and 6 elements for the second dimension

```
Redim aPeople(10,5)
```

The Redim method is used to increase or reduce the number of elements in the array specified. Arrays are zero-based (the first element is zero) so you resize the array using a number that is one less than the number of elements you actually want. The number of parameters passed is the number of dimensions of the array being resized.

---

## Rem

Rem any comment

Used to add comments to your code.

---

## Replace

Replace (String, String, String) As String

Replaces the first occurrence of a String with another String.

```
Dim result As String
```

```
result=Replace("The quick fox","fox","rabbit") //returns "The  
quick rabbit"
```

```
result=Replace("The quick fox","f","b") //returns "The quick box"
```

```
result=Replace("The quick fox","quick","") //returns "The fox"
```

---

## ReplaceB

ReplaceB (String, String, String) As String

Replaces the first occurrence of oldString in sourceString with newString.

ReplaceB is the byte version of Replace.

- If newString is an empty string (""), the ReplaceB function deletes the first occurrence of the oldString in the sourceString.
- If oldString is an empty string (""), the ReplaceB function returns an unchanged copy of the sourceString.

ReplaceB is case-sensitive; it treats sourceString as a series of raw bytes. It should be used instead of Replace when the string represents a series of bytes or when your application will run in a one-byte character set (such as the US system) and you want case-sensitivity.

---

## ReplaceAll

ReplaceAll (String, String, String) As String

Replaces all occurrences of a String with another String.

Dim result As String

result=ReplaceAll("xyxyxy","x","z") //returns "zyzyzy"

result=ReplaceAll("The quick fox"," ","") //returns "Thequickfox"

result="The Quick Fox"

result=result.ReplaceAll(" ","") //returns "The,Quick,Fox"

---

## ReplaceAllB

ReplaceAllB (String, String, String) As String

The ReplaceAllB function replaces all occurrences of oldString in sourceString with newString. ReplaceAllB is case-sensitive because it treats the source string as a series of raw bytes.

- If newString is an empty string (""), the ReplaceAllB function deletes every occurrence of the oldString in the sourceString.
- If oldString is an empty string (""), the ReplaceAllB function returns an unchanged copy of the sourceString.

ReplaceAllB is case-sensitive; it treats sourceString as a series of raw bytes. It should be used instead of ReplaceAll when the string represents a series of bytes or when your application will run in a one-byte character set (such as the US system) and you want case-sensitivity.

---

## Right

Right (String, Integer) As String

Returns the last n characters from the String specified.

Dim s As String

s=Right("Hello World", 5) //returns "World"

s="Hello World"

s=s.Right(5) //returns "World"

---

## RightB

RightB (String, Integer) As String

The RightB function returns bytes from the source string starting from the right



side (as the name implies). RightB treats source as a series of bytes rather than a series of characters. It should be used when source represents binary data. If you need to read characters rather than bytes, use the Right function.

---

## **Rnd**

Rnd As Double

Returns a randomly generated number in the range  $0 \leq \text{Rnd} < 1$ . The equivalent functionality is provided by the Random class as a special case. The Random class also provides additional options, such as a random number selected from a Normal distribution.

---

## **Round**

Round (Double) As Double

Returns the value specified rounded to the nearest Integer.

Dim d as Double

```
d=Round(1.499) //returns 1
```

```
d=Round(1.500) //returns 2
```

---

## **RTrim**

RTrim (String) As String

Returns the String data type passed with trailing (right side) whitespaces removed.

Dim s as String

```
s=RTrim(" Hello World ") //Returns " Hello World"
```

```
s=" Hello World "
```

```
s=s.RTrim //Returns " Hello World"
```

Rtrim uses the list of unicode “whitespace” characters at <http://www.unicode.org/Public/UNIDATA/PropList.txt>.

---

## **Select Case**

Select Case

Executes one of several groups of statements, depending on the value of an expression.

The Select Case statement is useful when there are several possible conditions

that must be checked. Unlike an If statement, the Select Case statement will exit as soon as it finds a matching Case expression and executes any statements that follow the Case expression up to the next Case expression. If there are no Case expressions that match, the elseStatements are executed. The expression Case Else can be used as a synonym for Else. The Case statement can accept several types of expressions. The expression can be a single value, a comma-delimited list of values, a function that returns a value, a range of values specified with the 'To' keyword, or an expression that uses the 'Is' keyword to do an equality or inequality test. You can combine types of expressions, separating them by commas. Here are some examples:

```
Case 2, 4, 6, 8 //several values
Case 2 To 5 //range of values using To
Case 2 To 5, 7,9,11 //Both separate values and range
Case myFunction(x) // a Function
Case Is >= 42 // greater than/equal to operator
Case Is <19 //less than operator

Dim d as New MessageDialog //declare the MessageDialog object
Dim b as MessageDialogButton //for handling the result

d.Icon= MessageDialog.GraphicCaution //display warning icon
d.ActionButton.Caption="Save"
d.CancelButton.Visible= True //show the Cancel button
d.CancelButton.Cancel= True//esc key works for Cancel
d.AlternateActionButton.Visible= True //show the "Don't Save"
button
d.Message="Save changes before closing?"
d.Explanation="If you don't save your changes, you will lose "
+"all that important work you did since your last coffee break."
b=d.ShowModal //display the dialog
Select Case b //b is a MessageDialogButton
Case d.ActionButton //determine which button was pressed.
//user pressed Save
Case d.AlternateActionButton
//user pressed Don't Save
Case d.CancelButton
//user pressed Cancel
End Select
```

---

## SetDeviceVar

Sets a Device Variable to a new Value.

**In a Device Driver, the syntax is**

SetDeviceVar(VarName,NewValue)

**In a Script, the syntax is**

SetDeviceVar(DeviceName,VarName,NewValue)

All Parameters are Strings

---

## SetGlobalVar

```
// All Parameters are Strings
SetGlobalVar(VarName,NewValue)
```

This Function call is not available in Device Drivers and Event Condition scripts, only in Tasks

---

## Sin

Sin (Double) As Double

Returns the sine of the value specified.

```
Dim d As Double
Const PI=3.14159265358979323846264338327950
d=Sin(0.5) //returns 0.4794255
d=Sin(30*PI/180) //returns .5
```

---

## SingleToStr

Converts a Single to a four byte single string

**This is the code behind the function call**

```
Sub SingleToStr(FloatVal as single) as String
```

```
//converts a single (i.e. 0.023) to a four byte float string
```

```
Dim mb As MemoryBlock = New MemoryBlock(4)
dim s,stmp as string
```

```
mb.SingleValue(0) = FloatVal
// automatic conversion between memoryblock and strings!!  =)
s = mb
stmp = mid(s,4,1)+mid(s,3,1)+mid(s,2,1)+mid(s,1,1)
return stmp
```

```
End Sub
```

---

## Sqrt

Sqrt (Double) As Double

Returns the square root of the value specified.

```
Dim d As Double
d=Sqrt(16) //returns 4
```

---

## Str

Str (Double) As String

Returns the String form of the value passed.

Dim s As String

```
s=Str(123) //returns "123"
s=Str(-123.44) //returns "-123.44"
s=Str(123.0045) //returns "123.0045"
Const Pi=3.14159265358979323846264338327950
s= Str(pi) // returns "3.141593"
s= Str(3141592653589012345) // returns "3141592653589012345"
```

---

## StrComp

StrComp (String, String, Integer) As Integer

Makes a binary (case-sensitive) or text (lexicographic) comparison of the two strings passed and returns the result.

The following example returns -1 because the two strings are the same in every way except in case.

```
StrComp("Spam", "spam", 1)
```

The following example returns -1 because in a text comparison of the two strings, string2 is greater than string1. The ASCII value of "s" is greater than the ASCII value of "S".

```
StrComp("Spam", "spam", 0)
```

---

## StrToHex

StrToHex (String) As String

Returns a String of hexadecimal numbers

dim s as string

```
s = HexToStr("ABC")
// Returns "414243", because "A" has ASCII code &h41 or 65
decimal,
//           "B" has ASCII code &h42 or 66 decimal etc.
```

---

## Tan

Tan (Double) As Double

Returns the tangent of the angle specified.

```
Dim d As Double
Const PI=3.14159265358979323846264338327950
d=Tan(45*PI/180) //returns 1.0
```

---

## Ticks

Ticks as Integer

Returns the number of ticks (60th of a second) that have passed since the user's computer was started.

```
Dim minutes As Integer
minutes=Ticks/60/60
MsgBox "Your computer has been on for"+ Str(minutes)+" minutes."
```

Because modern operating systems can stay running for so long, it's possible for the machine's internal counters to “roll over.” This means that if you are using this function to determine how much time has elapsed between two events, you may encounter a case where it appears that the stop time is prior to the start time.

---

## TimecodeToFramecode

returns a integer that contains the number of frames in a given timecode. The function uses the Global Framerate (Main Menu -> Options) to determine the frames per second. The following example converts a timecodeto a framecode.

```
dim fc as integer
fc = TimecodeToFramecode("10-05-12-21")
```

---

## Titlecase

Titlecase (String) As String

Returns the String passed to it with all alphabetic characters in Titlecase.

```
Dim s As String
s=Titlecase("tHe Quick fOX") //returns "The Quick Fox"
s=Titlecase("THE LAZY DOG") //returns "The Lazy Dog"
```

---

## Trim

Trim (String) As String

Returns the String passed with leading and trailing whitespaces removed.

```
Dim s As String
s=Trim(" Hello World ") //Returns "Hello World"
```

---

## Ubound

Ubound (array) As Integer

Returns the index of the last element in an array.

The Ubound function can be used to determine the last element of an array, but it can also be used to determine the size of an array. It may appear at first that the last element number and the size of the array are the same but in fact they are not. All arrays have a zero element. In some cases element zero is used and in other cases it is not. You will need to keep this in mind when using the Ubound function to determine the number of values you have in the array. If the array is zero-based, then element zero is used to store a value and you will have to add one to the value returned by the Ubound function to make up for it.

This example replaces each occurrence of X in an array with Y.

```
Dim i As Integer
For i=0 to Ubound(Names)
    If Names(i)="X" Then
        Names(i)="Y"
    End If
Next
```

---

## Uppercase

Uppercase (String) As String

Converts all characters in a String to uppercase characters.

```
Dim s As String
s=Uppercase("tHe Quick fOX") //returns "THE QUICK FOX"
s=Uppercase("the 5 lazy dogs") //returns "THE 5 LAZY DOGS"
```

---

## Val

Val (String) As Double

Returns the numeric form of a String.

```
Dim n As Integer
n = Val("12345") //returns 12345
n = Val(" 12345") //returns 12345
n = Val("123 45") //returns 123
```

```
n = Val(" &hFFF") //returns 4095
n = Val(" &b1111") //returns 15
```

The Val function stops reading the String at the first character it doesn't recognize as part of a number. All other characters are automatically stripped. It does recognize prefixes &o (octal), &b (binary), and &h (hexadecimal). However, spaces are not allowed in front of the ampersand. That is, " &hFF" returns 0, but " &hFF" returns 255. The CDbI function is the same as the Val function but is used when you need to pass a String that uses a character other than the period (.) as the decimal separator. It uses the decimal character specified by the operating system. For example, on Windows XP, it is set in the Regional and Language Options Control Panel. Val should generally be used to convert internal data, but not data entered by the user. Val is not international-savvy, but CDbI is. The CStr function is the same as the Str function but is used when you need to pass a number that uses a character other than the period (.) as the decimal separator. It uses the decimal character specified by the operating system. Val returns zero if string contains no numbers.

## Compiler Errors

Error Codes Compiler error numbers returned in errorNumber are shown below:

Error Number	Description
1	Syntax does not make sense.
2	Type mismatch.
3	Select Case does not support that type of expression.
4	The compiler is not implemented (obsolete).
5	The parser's internal stack has overflowed.
6	Too many parameters for this function.
7	Not enough parameters for this function call.
8	Wrong number of parameters for this function call.
9	Parameters are incompatible with this function.
10	Assignment of an incompatible data type.
11	Undefined identifier.
12	Undefined operator.
13	Logic operations require Boolean operands.
14	Array bounds must be integers.
15	Can't call a non-function.
16	Can't get an element from something

	that isn't an array.
17	Not enough subscripts for this array's dimensions.
18	Too many subscripts for this array's dimensions.
19	Can't assign an entire array.
20	Can't use an entire array in an expression.
21	Can't pass an expression as a ByRef parameter.
22	Duplicate identifier.
23	The backend code generator failed.
24	Ambiguous call to overloaded method.
25	Multiple inheritance is not allowed.
26	Cannot create an instance of an interface.
27	Cannot implement a class as though it were an interface.
28	Cannot inherit from something that is not a class.
29	This class does not fully implement the specified interface.
30	Event handlers cannot live outside of a class.
31	It is not legal to ignore the result of a function call.
32	Can't use "Self" keyword outside of a class.
33	Can't use "Me" keyword outside of a class.
34	Can't return a value from a Sub.
35	An exception object required here.
36-39	Obsolete.
40	Destructors can't have parameters.
41	Can't use "Super" keyword outside of a class.
42	Can't use "Super" keyword in a class that has no parent.




# Timestrips

Timestrips are a kind of Timeline. The main difference is, that a Timestrip is vertical arranged. For us, this seems to be more practical for programming. It is possible to run more than one Timestrip at a time.

Timestrips are controlled by external timecode. (If no external timecode is available, the internal timecode can be used). To tell the system where to get the timecode from, a Timecode Source device has to be configured. Usually, this is a timecode reader such as Alpermann+Velte TC 60.

Timestrips can use Chase Devices. That are devices that are automatically locked to the external timecode.

To add a cue to a Timestrip, click *Add Position* to create a new row in the Timestrip.



## Timestrip user interface


1. Timestrip list: lists all available Timestrips.
2. Timestrip view: This is the visual representation of the Timestrip. The first column hold the timecode for a cue. A cue can consist of up to 48 tracks, each track representing an individual command. A track is not linked to a device, so having commands from different devices within one track is OK. To edit a timecode double click on it. To edit a cue, double click on the cues row and column.
3. Add Track adds one more track to the timestrip.
4. Remove Track removes the last track.
5. The Position field changes the current position in the Timestrip. By entering a value here and pressing the Enter / Return key, all Chase Devices will locate to this position. The timecode entered in the Position field is also used for the Add Position button (see 7. Add Position).
6. These buttons change the Position value.
7. The Add Position button creates a new row in the Timestrip table. The content of the Position field is used as new timecode value.

8. Absolute Offset moves the Timestrip to another position. If, for example, an absolute offset of one hour is set, all the timecode values are changing and one hour is added to them.
9. Relative Offset leaves the timecode in the table unchanged. It means that firing a cue is delayed (if offset is positive) or ahead (if offset is negative)
10. The Chase Mode area determines the Chase Devices and Timecode Master source

## Create Timestrip

A new Timestrip can be created by the Timestrips list context menu.


Alternatively use the  Icon to do this.




The Position field holds the timecode value for a new cue. Add Position creates a new row in the timestrip table.



*empty Timestrip*




To add a cue, select a command and press the Add Cmd button.




## Chase Devices

The Chase area determines the chase devices and the master timecode. Chase devices follow the external (or internal) timecode automatically, as far as the timestrip is running. To configure this feature, the following steps have to be carried out.



## 1. Determine the Timecode Master

Via *Timecode Source* button, a dialogue is opening, allowing to select a device as timecode master.



In this case, we use a timecode reader interface (Alpermann + Velte TC60 RL Timecode Reader). To complete the selection, don't forget to choose a channel for the device as well (tc60 in this example). If there is no external timecode reader available, one can choose Internal Timecode as timecode source.

## 2. Start TC (only with Internal Timecode)

Determines the start value of the internal timer. This is where the Timestrip starts.

## 3. Set End TC (only with Internal Timecode)

Determines the end value of the internal timer. This is where the Timestrip ends.


#### 4. Framerate of the Timecode

#### 5. Preroll Frames

Preroll Frames determine the time, the system needs for synchronization. They depend on the device that is used as chase device. The quicker the chase device can locate a new position, the less Preroll Frames can be necessary. For today's harddisk players, a value between 5 and 15 Frames should be sufficient.

#### 6. Select the Chase Devices

Add Device opens a dialogue to choose the chase devices.



To select a chase device, select the device and the channels.

#### 7. Remove the selected chase device

#### 8. Chase Device List

A list with all configured chase devices

#### 9. Run from Current TC (only with Internal Timecode)

The timestrip start from the position entered in the Position field.

#### 10. Loop (only with Internal Timecode)

Play endless. If you are using an external timecode, the timecode source has to do the loop if you want one.

# Events

An event in V-Control works as a trigger. If the event occurs, a defined task is executed as event handler. All events are triggered by a variable change. This could be a device variable, a system variable or a global variable.

The device drivers collect information about the connected device and represent the status of the device in device variables. Each time a variable changes an event is fired. If there is an event handler for this event then the task that handles the event is fired. Device Events allow V-Control to respond on external events triggered by a connected device. If, for example, a temperature sensor send a message that a limit is reached, or a motion sensor detects a person and notify this, or a players position has changed, V-Control can launch a task and react on this event.

To trigger an event, a condition script determines if the event handling task is fired or not. Lets say we have a temperature sensor and we want to start a fan if the temperature is over 35°C. The fan should stop if the temperature is less then 30°C. So we have two conditions to check and determine which task to start.

Condition 1 is: if Temperature > 35 then start fan Condition 2 is: if Temperature < 30 then stop fan

## Device Variable Change Events

These events initiated by the external attached devices, e.g. a liquid level sensor reports a new level or a light barrier detects a break. The sensor send a message via the channel (or the device driver requests the status periodically), and V-Control looks if there is an event handler. If an event handler is found, it checks the condition and fire the task if the condition is true.


The screenshot displays the V-Control software interface. On the left, a table lists device variables for the 'ioLogic\_E1214\_v4' device. The 'Var Name' column lists variables like Received, Status, K0Status, K1Status, K2Status, K3Status, K4Status, K5Status, D0Status, D1Status, D2Status, D3Status, D4Status, and D5Status. The 'Value' column shows their current states, such as 'Mv&h00&h...', 'OK', '1', '0', etc. The 'ioLogic\_E1214\_v4' device is highlighted in blue. On the right, the 'Events' tab is active, showing a 'Commands' list with 'SetSingleRelay' at position 030 and 'SetMultipleRelays' at position 040. A 'Unit ID' dropdown is set to '0'. At the bottom, there are buttons for 'Add Cmd', '?', and 'Run Cmd'. Below the interface, a status bar indicates 'Engine Event Message Stack: 1'.

Devices	Var Name	Value
System_v4	Received	Mv&h00&h...
RemoteScreenReceiver_v4	Status	OK
RemoteScreenSender_v4	K0Status	1
ioLogic_E1214_v4	K1Status	0
PanasonicPT_Series	K2Status	1
EpsonProjector	K3Status	0
DVS_Pronto	K4Status	1
	K5Status	0
	D0Status	0
	D1Status	0
	D2Status	0
	D3Status	0
	D4Status	0
	D5Status	0


Lets do an example:

The ioLogic E1214 is a TCP controlled box from Moxa. It uses the Modbus TCP protocol. It has 6 Relays and 6 digital inputs. Now we want to run a task if digital input 1 gets High. Select the device and the device variable D0Status. Then click the *Create Condition Template* button. V-Control creates a condition script

that has to be edited so that the condition is true if D0Status = 1.



The first line of the condition script is a comment. It is shown in the *Eventlist* and is used as a hint for the programmer. Change the condition script as shown below.



Click the *Add Event* button. Now there is a new entry in the Eventlist. The next step is to assign a task to this event. In the context menu (click right) of the event list select *Assign Task*. The list now looks like this:

Event List		Search:			
ID	Device	Var Na...	Condition	Task	Block
0	ioLogic_E12...	D0Status	//If D0Status = "1" then Condition = t...	Example	1000

Now, if the variable D0Status of the device changes from 0 to 1, the task assigned to the event is fired.

## The Condition Script

The first row of the condition script is a comment and shown in the Eventlist. Write whatever is helpful to have a good hint what the script is doing.

The second row

```
Dim D0Status as String
```

creates the local variable D0Status. This is necessary because we don't have direct access to a device variable.

in

```
D0Status = GetDeviceVar("ioLogic_E1214_v4","D0Status")
```

the content of the device variable D0Status is assigned to the local variable D0Status. The GetDeviceVar function accept only strings as parameters, so the device name and the variable name have to be surrounded by “.

The last row checks if the condition is true. The condition is always false by default and changes only to true if explicit set.

```
If D0Status = "1" then Condition = true
```

## The Condition Editor

Device Events

☒ Use Device Variable ☐ Use Global variable Create Condition Template

Condition -1 After fired block for ms: 1000

```
//If D0Status = "1" then Condition = true  
Dim D0Status as String  
D0Status = GetDeviceVar("ioLogic_E1214_v4","D0Status")  
If D0Status = "1" then Condition = true
```

Compiler Message: Update Event Add Event

The Condition Editor tries to support the programmer in creating the script. As explained above, the *Create Condition Template* button creates a script that is used as first step.

Variable change events can occur from device variables and global variables. If then *Use Device Variable* option is set, a device variable is used. For global variables use the *Use Global Variable* option.

Device variables can change very frequently. A variable containing a timecode changes every 33 ms (30 fps). If you have a condition such as

```
Dim Positionas string
```



```
Dim iPosition,iTarget as Integer
```

```
Position = GetDeviceVar("DVS_Pronto","Position"
```

```
iTarget = TimecodeToFramecode("10-12-21-10")
```

```
iPosition = TimecodeToFramecode(Position)
```

```
if (iPosition >= iTarget) and (iPosition < Target +10) then
```

```
Condition = true
```


This script returns true if the Position is between 10-12-21-10 and 10-12-21-20. It might be that V-Control does not detect all of the 10 valid variable changes, but for sure more then one. In this case the Task that is linked to the event is fired frequently during this period. It could happen that V-Control tries to fire the task again while it is still running. For that reason we have the *After fired block for ms*. Here you can enter the time in ms the event should not fire again. After the time it will fire again. This value is 1000ms (1 Second) by default.

If your script causes compile errors the line with the error is marked in the script and an error message is shown (*Compiler Message*).

A double click in the eventlist loads the event again. To change the event click the *Update Event* button, to create a new click the *Add Event* button.

## Calendar Events

To create events that depend on a Date, Time or Time interval the System device is used. To add a System device open the *Device Setup* dialog by clicking the *Device* button in the toolbar. Search for System\_v4.



The System Device is the only device that does not need a channel. It has no commands, only status variables representing Date and Time. The Time is in the format HH:MM:SS:FF (FF = Frames). The framerate is determined in the Options Dialog System page.

*DayOfWeek* is the current weekday (1=Sunday..7=Saturday)

To create an event that fires weekdays at 9:00 AM we have to check the current Time and the DayOfWeek. Because the DayOfWeekVariable changes only every 24 hours, we use the *CurrentTime* variable as trigger.

Select the *CurrentTime* variable, select the *Events* tab and pres the *Create Condition Template* button.

Change the Template to

```
//If CurrentTime = "09:00:00 " and DayOfWeek >1 and < 7 then
Condition = true
Dim CurrentTime as String
CurrentTime = GetDeviceVar("System_v4","CurrentTime")
//ignore frames, analyse the part "HH:MM:SS" only
If Mid(CurrentTime,1,8) = "09:00:00" then
    Dim DayOfWeek as Variant
    DayOfWeek = GetDeviceVar("System_v4","DayOfWeek")
    if DayOfWeek >1 and DayOfWeek < 7 then condition = true
end
```

Maybe one is wondering about *Dim DayOfWeek as Variant*. If *DayOfWeek* was declared as string, then an operation such as *if DayOfWeek > 1* would cause a compile error, because a string cannot be compared with an integer. A variant behaves as string if the content is a string, or as integer if the content can be converted to integer. So the string "1" can be converted to the integer 1. This happens automatically.


Now the event is fired 25 Times (from "09:00:00:00" - "09:00:00:24" at 25 fps). Because we want to ensure that the event is only fired ocne, set the *After fired block for ms* to 2000 ms. Now press the *Add Event* Button

Finally, after assigning a task to the event, the result is

# Simple GUI

## Playlist

Via *Playlist* tool button or main menu *Playout -> Playlist* the Playlist window pops up.




The left table lists all available tasks (Scripts, Cuelists and Timestrips). To fill the Playlist (right table) move the tasks in the left list via drag and drop to the right table. To launch a task, double click on it. Alternatively, a selected task can be launched by pressing the space bar. A shortcut key is assignable via playlist context menu as well as a comment.

If the button Stop all Tasks before playing a new one is pressed, then all running tasks are stopped before the new one launches.

# CallButtons

CallButtons provide another way to have a GUI for end users. Click *Playout->CallButtons* to open the CallButton window.




To add a new button click right on a free space and select the *Add Button* context menu. Each time the *Add Button* menu is clicked a new button occurs on the CallButton surface.

To assign a task to a button right click on the button and select the context menu *Select Task*. This opens a window with all available tasks. Select one and click *Add*. By default, the taskname is used as caption for the button. If you want another caption then the taskname you can click right on the button and select *Change Caption*

# V-Control Designer

V-Control Designer is software that is used to create Graphical (touch) User Interfaces for V-Control. It communicates with the Remote Panel Server via TCP, and up to 5 V-Control Designer instances can have simultaneous access to a Remote Panel Server. The Remote Panel Server has two connections to V-Control Devices, the RemotePanelReceiver and the RemotePanelSender. Because V-Control, the Remote Panel Server and V-Control Designer communicate via TCP, they can run on the same machine or on different ones.



While V-Control and the Remote Panel Server is multi-platform software (Windows, MAC OSX and Linux) V-Control Designer is Windows only at the moment. Nevertheless, V-Control Designer can operate with Remote Panel Server running on a Linux or MAC OS computer (and of course Windows). Only V-Control Designer itself has to run in a Windows environment.

## Installation

### Remote Panel Server

Unzip the downloaded file and copy it to a directory with users write permissions. Then launch the exe file.

### V-Control Designer

Unzip the downloaded file and copy it to a directory with users write permissions. Then run vcredist\_msvc2015\_x64.exe that is located in the V-Control Designer directory. Then launch the exe file.

## Licensing

V-Control Designer is not open source such as V-Control. However, the program is free to use. There are no license fees for V-Control Designer, but for the Remote Panel Server, and this server is mandatory. Therefore you need to buy


a license for the Remote Panel Server to use V-Control Designer. A license is only valid for one instance of the Remote Panel Server, and only one instance can run on a computer.

The Remote Panel server runs in Demo mode without a license. That means that every 30 minutes the network connection will be closed and the software must restart. There are no other restrictions. If purchased a license, use the hardware key (USB thumb drive) and the Server will run in licensed mode.

## Hardware License Key

The Remote Panel Server needs hardware dongle as license key. The dongle will be send after purchase. Alternatively use the *File->License Request* menu to create a license request file:

- Purchase V-Control Remote Panel Server
- With the purchase, make a note that you will send a license request key later. Alternatively send the license request key with the purchase as note.
- Download and start the RemotePanelServer
- Connect a USB thumb drive to your computer
- select *File->License Request*



- Click the Get Drives button
- Select the USB drive in the drop down list right of that button
- Click Create License Request
- Copy the Key and send us an Email with that key
- We create a license file and send it via Email back to the purchaser
- Copy the file in the root directory of the USB drive used for the license request.

**It will only work with the USB drive used for the request. Using another drive has the same result as using no key.**

# Remote Panel Server

There is no direct communication between V-Control and V-Control Designer. The Remote Panel Server works as intermediary between the two programs.

V-Control Remote Panel Server

File Edit

Display Server Port: 30407 Open Max. Log Count: 25

Network Interface: 0:192.168.1 Enable Log

V-Control Sender Port: 30408 Type: D Send to V-Control

Network Interface: 0:192.168.1 JoinNb: Send To Displays

V-Control Receiver Port: 30409 Value:


Network Interface: 0:192.168.1 License Key = 051077000000016D0

Client	Type	JoinNb	Value
--------	------	--------	-------

First start the Remote Panel Server

The Remote Panel Server opens 3 server ports. The Display Server Port is used by V-Control Designer (up to 5 at the same time). V-Control Sender Port and V-Control Receiver Port are used by V-Control devices.

V-Control needs two new devices, The RemoteScreenSender and RemoteScreenReceiver. Create TCP-Client channels with the IP Address of the Remote Panel Server and the ports for Sender and Receiver.



## Join Number Concept in Detail

To interact with the V-Control Designer widgets, (buttons, labels, sliders etc.) a concept of join numbers is used. Join numbers define a connection to / from a widget. There are three different types of join numbers:


1. Digital Joins: They can have a value of 0 or 1.
2. Integer Joins: Any Integer value
3. String Joins: Any type of characters

Join numbers for each type can be between 1 and 999. So you have 999 digital joins, 999 integer joins and 999 string joins. All V-Control Designers connected to one Remote Panel Server share these join numbers. So if you have more than one Designer connected to the Remote Panel Server, and they show different GUI's (Graphical User Interface), take care that the join numbers don't overlap.

But in some cases it can be useful to share some join numbers on different GUI's. If you have information that is needed on all displays, then you can use a single string join number and have labels on all GUI's with this number. Then the information appears everywhere.


Below there is a button with some of its properties. Notice the second one, Digital Join. Because a button can only have the state On or Off, the digital Join represent its state.






If the button is pressed, it sends a message with its type (Digital in this case), join number and 1 as value. If the button is released it sends the same message but 0 as value.

In V-Control, there is a device RemoteScreenReceiver. Per default, this device has device variables D001..D100 for digital joins, I001-I100 for integer joins and S001..S100 for string joins. If more join numbers needed add them in the Device Editor




If V-Control Designer sends a message with a join number and a value, then the RemoteScreenReceiver updates a device variable (D013 in this example). This generates an event, and we can use this event to run a task.



A detailed description how events work in V-Control is at Events


Lets Do the other way. Below is a label with the string String Join Caption 1.



We can now use the device RemoteScreenSender to send a message to this join number. The content of this message will be shown in the label.


Maybe you notice that the label has additional string joins. String Join *Back Color*, String Join *Border Color* and String Join *Text Color* can receive messages to change the corresponding colors.

The RemoteScreenSender device has commands to send messages to the Remote Panel Server



The command SendString send as message to a string join, in this case join


number 1 which we used for the caption join of the label. If we run this command, the label changes its caption.



More Information about RemoteScreenReceiver and RemoteScreenSender can be found at Device Drivers.

## Manage Join Numbers

In large projects it is easy to lose track of the join numbers. For that reason, V-Control can help managing join numbers. In V-Control, click the Join List tool button.



This list is used to make notes what a join number is used for. If you have a

button with join number 1, and the *RemoteScreenReceivers* device variable D001 change event is used to trigger a task that turns on a projector, edit the row with *D001* in the following way:

Join Nb	Name	Comment
D001	onBtnProjectorOn	Turns on projector and wait 5 seconds
D002		
D003		

It is good practice to give the widgets meaningful names. The task that handles the change event has the same name with prefixed “on”. Use the comment column for further useful information. Because the list could be very long, the Search field helps to find a row of interest. Anything typed in here that matches any row content works as a filter. Only rows that match the search field content are shown.

D023

Create Default List

Join Number:

Add Row

At the bottom of the Join List, the Create Default List button creates a default list of join numbers (D001..D100, I001..I100 and S001..S100). If more join numbers are needed enter a new one in the Join Number field. The format is D101 for a new digital join number 101. I221 creates an integer join with number 221 and S123 a new string join with number 123. Click the Add Row button to insert the new join number.

## GUI Overview




The Main Window is divided into three parts:

1. The Library (left) Here are the widgets that can be dropped to the page area. These widgets are used to build the GUI.
2. Page Area (center) This is the area where you drop and position your widgets.
3. Project Settings / Inspector (right) Here you can set up the project and customize the widgets.

Click the Run menu item to switch to run mode.

## Project Settings



**Display Server IP:** To establish a connection between V-Control Designer and Remote Panel Server, you need to set up the TCP connection. Display Server IP contains the IP Address of the Remote Panel Server. If both, Remote Panel Server and V-Control Designer running on the same system, this should be localhost (127.0.0.1). In other cases the use the real address.

**Port:** The TCP port that is used by Remote Panel Server to connect to Displays (Display Server Port).

**Full Screen:** If checked, V-Control Designer will cover the whole screen if switched to Run mode. There will be no window decoration. To exit the run mode if full screen view, press ESC.

**H Grid, V Grid:** In Edit Mode, the user can display a grid that helps to position and align the widgets. H Grid and V Grid determine the distance between the grid lines.

**Grid Color:** Determines the color of the grid.

**Show Grid:** If checked, the grid is shown

**Magnetic Grid:** If checked, widgets will align to the grid if you change their


position by dragging them.

**H Size, V Size:** Determines the size of all pages in a single project. Usually this should match the Display size if you want to run in Full Screen mode.

**Add Page, Delete Page** V-Control Designer can use multiple pages within one project. Here you can add new ones or delete existing ones.

## Settings

Main Menu File → Settings




**Default Project** Press the Select button to choose a project that is loaded at startup.

**Autostart Default Project** If a valid project is loaded by default, enabling this check box will initiate run mode at startup.

## Pages

A V-Control Designer project consist of one or more pages. A page act as container for widgets and can use the entire screen in run mode if Full Screen is selected.


To add or delete pages switch to Project Settings.



### Page Properties:

To access the page properties select the Inspector and click on an empty area in the page. Then you can change the page Name and Back Color. The name has to be unique.

# Buttons




Button properties are:

- Name: The name of the button. Try to use meaningful names, this will help in complex projects to keep the overview.
- Digital Join: The join number for the button pressed and release event. If pressed, this join number will have the value 1, if released then 0. The A button automatically selects a free join number.
- Caption On: Button caption in pressed state
- Caption Off: Button caption in unpressed state
- Radius: If  $> 0$  then the button has round corners.
- Back Color Off: The back color of the button in unpressed state
- Border Color Off: The border color of the button in unpressed state
- Text Color Off: The Text color of the button in unpressed state
- Back Color On: The back color of the button in pressed state
- Border Color On: The border color of the button in pressed state
- Text Color On: The Text color of the button in pressed state
- Align: Alignment of the caption
- Top, Left, Width, Height: Position and size of the button
- Z: The Z-Order of the button. The higher this value, the more on top the widget is displayed if overlapping with other widgets.
- Resend Received: If a widget receive a message, then it can send the message back the message to the RemoteScreenReceiver. Imagine the button receives a message with value 0, the message was sent from the

RemoteScreenSender. Then the RemoteScreenreceiver doesn't know that the value has changed and does not update the corresponding device variable.

- Font: The font of the Caption
- Size: Font size of the caption
- Bold, Italic, Underline: Style of the Caption
- Image Off, Image On: Image to show in unpressed and pressed state
- Scale to fit: Scales the image that it fits in the widgets dimensions.
- Keep Aspect: Keep aspect ratio of the image
- Goto Page: Switch to another Page
- Mode: Normal: If pressed, it automatically gets unpressed. Toggle: If pressed, it stays pressed until it was pressed again. One Time: If pressed it stays pressed. The only way to reset is to send a message with value 0.

## Progress Bar




- Name: The name of the widget. Try to use meaningful names, this will help in complex projects to keep the overview.
- Integer Join: The join number to set the progress. The A button automatically selects a free join number.
- String Join Back Color: The back color of the progress bar. Color values are in the format AA,RR,GG,BB. AA = alpha (00..FF), 00 means transparent, FF full visible, RR = red (00..FF), GG= green (00..FF) and BB = blue (00..FF). All Color values are two digit hex numbers.
- String Join Border Color: The border color of the progress bar
- String Join Inner Color: The inner color of the progress bar. Use all the String Color Joins to change the color of the widget by V-Control.
- Min: The minimum integer value that the progress bar can show (no progress)
- Max: The maximum integer value that the progress bar can show (full progress)
- Top, Left, Width, Height: Position and size of the button



- Z: The Z-Order of the button. The higher this value, the more on top the widget is displayed if overlapping with other widgets.
- Resend Received: If a widget receive a message, then it can send the message back the message to the RemoteScreenReceiver. Imagine the button receives a message with value 0, the message was sent from the RemoteScreenSender. Then the RemoteScreenreceiver doesn't know that the value has changed and does not update the corresponding device variable.


## Label



- Name: The name of the widget. Try to use meaningful names, this will help in complex projects to keep the overview.
- Caption: The text that is displayed
- String Join Caption: The join number to set the Caption.
- String Join Back Color: The back color of the label. Color values are in the format AA,RR,GG,BB. AA = alpha (00..FF), 00 means transparent, FF full visible, RR = red (00..FF), GG= green (00..FF) and BB = blue (00..FF). All Color values are two digit hex numbers.
- String Join Border Color: The border color of the label
- String Join Text Color: The Text color of the label. Use all the String Color Joins to change the color of the widget by V-Control.
- Back Color: The back color of the label. Color values are in the format AA,RR,GG,BB. AA = alpha (00..FF), 00 means transparent, FF full visible, RR = red (00..FF), GG= green (00..FF) and BB = blue (00..FF). All Color values are two digit hex numbers.
- Border Color: The border color of the label

- Text Color: The Text color of the label.
- Align: Text alignment
- Top, Left, Width, Height: Position and size of the button
- Z: The Z-Order of the button. The higher this value, the more on top the widget is displayed if overlapping with other widgets.
- Resend Received: If a widget receive a message, then it can send the message back the message to the RemoteScreenReceiver. Imagine the button receives a message with value 0, the message was sent from the RemoteScreenSender. Then the RemoteScreenreceiver doesn't know that the value has changed and does not update the corresponding device variable.
- Font: The font of the Caption
- Size: Font size of the caption
- Bold, Italic, Underline: Style of the Caption
- Multilie: Show multiple lines of text


## Group Box



- Name: The name of the button. Try to use meaningful names, this will help in complex projects to keep the overview.
- Caption: The text that is displayed
- Back Color: The back color of the label. Color values are in the format AA,RR,GG,BB. AA = alpha (00..FF), 00 means transparent, FF full visible, RR = red (00..FF), GG= green (00..FF) and BB = blue (00..FF). All Color values are two digit hex numbers.
- Border Color: The border color of the label
- Text Color: The Text color of the label.
- Align: Text alignment
- Top, Left, Width, Height: Position and size of the button
- Z: The Z-Order of the button. The higher this value, the more on top the widget is displayed if overlapping with other widgets.
- Font: The font of the Caption


- Size: Font size of the caption
- Bold, Italic, Underline: Style of the Caption

## Image



- Name: The name of the widget. Try to use meaningful names, this will help in complex projects to keep the overview.
- String Join (URL): Send the path of an image to change the image by V-Control
- Back Color: The back color of the widger. Color values are in the format AA,RR,GG,BB. AA = alpha (00..FF), 00 means transparent, FF full visible, RR = red (00..FF), GG= green (00..FF) and BB = blue (00..FF). All Color values are two digit hex numbers.
- Border Color: The border color of the widget
- Top, Left, Width, Height: Position and size of the button
- Z: The Z-Order of the button. The higher this value, the more on top the widget is displayed if overlapping with other widgets.

## Text Input




- Name: The name of the widget. Try to use meaningful names, this will help in complex projects to keep the overview.
- Text: The text that is displayed
- String Join Caption: The join number to set the Text.
- String Join Back Color: The back color of the label. Color values are in the format AA,RR,GG,BB. AA = alpha (00..FF), 00 means transparent, FF full visible, RR = red (00..FF), GG= green (00..FF) and BB = blue (00..FF). All Color values are two digit hex numbers.
- String Join Border Color: The border color of the label
- String Join Text Color: The Text color of the label. Use all the String Color Joins to change the color of the widget by V-Control.
- Back Color: The back color of the label. Color values are in the format AA,RR,GG,BB. AA = alpha (00..FF), 00 means transparent, FF full visible, RR = red (00..FF), GG= green (00..FF) and BB = blue (00..FF). All Color values are two digit hex numbers.
- Border Color: The border color of the label
- Text Color: The Text color of the label.
- Top, Left, Width, Height: Position and size of the button
- Z: The Z-Order of the button. The higher this value, the more on top the widget is displayed if overlapping with other widgets.
- Resend Received: If a widget receive a message, then it can send the message back the message to the RemoteScreenReceiver. Imagine the button receives a message with value 0, the message was sent from the RemoteScreenSender. Then the RemoteScreenreceiver doesn't know that the value has changed and does not update the corresponding device

variable.

- Font: The font of the Caption
- Size: Font size of the caption
- Bold, Italic, Underline: Style of the Caption
- Multiline: Show multiple lines of text

## Combo Box



Name: The name of the widget. Try to use meaningful names, this will help in complex projects to keep the overview. Edit Items: Opens an editor to edit the items in the combo box Integer Join: The join number to select an item. Back Color: The back color of the label. Color values are in the format AA,RR,GG,BB. AA = alpha (00..FF), 00 means transparent, FF full visible, RR = red (00..FF), GG= green (00..FF) and BB = blue (00..FF). All Color values are two digit hex numbers. Border Color: The border color of the label Text Color: The Text color of the label. Top, Left, Width, Height: Position and size of the button Z: The Z-Order of the button. The higher this value, the more on top the widget is displayed if overlapping with other widgets. Font: The font of the Caption Size: Font size of the caption Bold: Style of the Caption


### Spin Button

- Name: The name of the widget. Try to use meaningful names, this will help in complex projects to keep the overview.
- Integer Join: The join number
- Min: The minimum integer value
- Max: The maximum integer value
- Top, Left, Width, Height: Position and size of the button
- Z: The Z-Order of the button. The higher this value, the more on top the widget is displayed if overlapping with other widgets.
- Resend Received: If a widget receive a message, then it can send the message back the message to the RemoteScreenReceiver. Imagine the button receives a message with value 0, the message was sent from the

RemoteScreenSender. Then the RemoteScreenreceiver doesn't know that the value has changed and does not update the corresponding device variable.

- Font: The font of the items
- Size: Font size of the items
- Bold: Style of the items


## Slider



- Name: The name of the widget. Try to use meaningful names, this will help in complex projects to keep the overview.
- Integer Join: The join number
- Min: The minimum integer value that the progress bar can show (no progress)
- Max: The maximum integer value that the progress bar can show (full progress)
- Orientation: Horizontal or vertical orientation
- Back Color: The back color of the widget. Color values are in the format AA,RR,GG,BB. AA = alpha (00..FF), 00 means transparent, FF full visible, RR = red (00..FF), GG= green (00..FF) and BB = blue (00..FF). All Color values are two digit hex numbers.
- Border Color: The border color of the widget
- Inner Color: The inner color of the widget.
- Handle Color: Color of the handle
- Scale Ticks: every Scale Ticks pixel a marker is set
- Show Scale: Show or hide the scale
- Sep Width: Minimum width of a step
- Knob Image: Image for the handle

- Inline Image: image for the inner part
- Top, Left, Width, Height: Position and size of the button
- Z: The Z-Order of the button. The higher this value, the more on top the widget is displayed if overlapping with other widgets.
- Resend Received: If a widget receive a message, then it can send the message back the message to the RemoteScreenReceiver. Imagine the button receives a message with value 0, the message was sent from the RemoteScreenSender. Then the RemoteScreenreceiver doesn't know that the value has changed and does not update the corresponding device variable.

The image properties of the slider allow custom sliders. It depends only on the graphical skills how they look.



## Ellipse

Library

Page 1

Group Box

Button

Label

V-Controller

Image View

Text Input

Spin Button

Inspector

Project Settings

Ellipse

Name

Ellipse 1

String Join Back Color

1

String Join Border Color

0

Back Color

ff432b91

Border Color

ff6ea428

Top

96

Left

380

Width

143

Height

100

Z

0


Resend Received

☐

- Name: The name of the widget. Try to use meaningful names, this will help in complex projects to keep the overview.
- String Join Back Color: The back color of the label. Color values are in the format AA,RR,GG,BB. AA = alpha (00..FF), 00 means transparent, FF full visible, RR = red (00..FF), GG= green (00..FF) and BB = blue (00..FF). All Color values are two digit hex numbers.
- String Join Border Color: The border color of the label
- Back Color: The back color of the label. Color values are in the format AA,RR,GG,BB. AA = alpha (00..FF), 00 means transparent, FF full visible, RR = red (00..FF), GG= green (00..FF) and BB = blue (00..FF). All Color values are two digit hex numbers.
- Border Color: The border color of the label
- Top, Left, Width, Height: Position and size of the button
- Z: The Z-Order of the button. The higher this value, the more on top the widget is displayed if overlapping with other widgets.

The Ellipse is often used as a background for other widgets to visualize a function group.

## Rectangle



- Name: The name of the widget. Try to use meaningful names, this will help in complex projects to keep the overview.
- Radius: Corner radius.
- String Join Back Color: The back color of the label. Color values are in the format AA,RR,GG,BB. AA = alpha (00..FF), 00 means transparent, FF full visible, RR = red (00..FF), GG= green (00..FF) and BB = blue (00..FF). All Color values are two digit hex numbers.
- String Join Border Color: The border color of the label
- Back Color: The back color of the label. Color values are in the format AA,RR,GG,BB. AA = alpha (00..FF), 00 means transparent, FF full visible, RR = red (00..FF), GG= green (00..FF) and BB = blue (00..FF). All Color values are two digit hex numbers.
- Border Color: The border color of the label




- Top, Left, Width, Height: Position and size of the button
- Z: The Z-Order of the button. The higher this value, the more on top the widget is displayed if overlapping with other widgets.

The Rectangle is often used as a background for other widgets to visualize a function group.


## RemoteScreenSender

The RemoteScreenSender is used to send commands and / or information to a V-Control Designer instance. V-Control Designer elements (buttons, sliders, labels etc.) are referenced by join numbers. The RemoteScreenSender can send simple messages and device variables.

### Sending Device Variables




To send a device variable, the RemoteScreenSender needs to know which device and which variable. To get a list of all available devices, the *RefreshDevices* command is used. Switch to *Run* mode and press the *Run Cmd* button if the *RefreshDevices* command is selected. Nothing happens for now, but next select the *RefreshDeviceVars* command. The drop down box *DeviceName* now holds a list of all devices in the current project.




The *RefreshDevices* command has to be executed only once, or if devices were added or deleted from the current project. The list is stored with the project file.


Next we need to get the device variables for a selected device. Select the *RefreshDeviceVars* command and select a device. then switch to *Run* mode and push the *Run Cmd* button.




Again nothing seems to happen. But now select the *SendDeviceVar* command.



The *DeviceName* parameter is preselected with the device chosen with the *RefreshDeviceVars* command. Now select a device variable in the *DeviceVar* parameter box.



Next step is to choose to which join number in which format the content of the device variable is send.




One may wonder why we choose a string join number here. If we want to show the lamp hours of a projector, we usually use a label to show the information. In this case we have a label with the string join number 6 for caption. If we send this as integer, we need a widget with an integer join such as slider or progress bar.


## Sending User Data

Another way to send messages to a V-Control Designer instance is to use the *SendDigital*, *SendInteger* and *SendString* commands.

If used in *Cuelists*, the only option is to enter the data direct as command



If used in *Scripts*, we can process the data that is send.



In the example above we want to send the Temperature value of a weather station to a progress bar. But the Temperature comes in a format such as "20,5". If multiplied by 10, the result is 205, which is an integer value. Imagine we have a progress bar with minimum value -300 and maximum value 500, then it can now show Temperatures from -30 to 50°C.

## Getting Join Values

Another method to update the user variables of the RemoteScreenReceiver is to send a Get message to V-Control Designer. This is done by the *GetDigital*, *GetInteger* and *GetString* command. If one of these commands is sent from the *RemoteScreenSender*, the Designer send a message to the *RemoteScreenReceiver* that updates the device variable. If the variable

changes, an event is fired.

## RemoteScreenReceiver

Devices	Var Name	Value
PJLink	Received	
ioLogik E1214	D001	
HSW Drehscheiben Mo...	D002	
V7300_1	D003	
V7300_2	D004	
V7300_3	D005	
V7300_4	D006	
V7300_5	D007	
V7300_6	D008	
V7300_7	D009	
V7300_8	D010	
RemoteScreenRec	D011	
RemoteScreenSender	D012	
System_v4_1216	D013	
VControlNode_1218	D014	
OSC_1220	D015	
Soloist2_v4_1222	D016	

The RemoteScreenReceiver does not have any commands. By default, it has the device variables *D001..D100*, *I001..I100* and *S001..S100*. The RemoteScreenReceiver is only used to generate events on a variable change. How to create events is described in the Events chapter.

## System

The System device is used to provide Time and Date information.

Devices	Var Name	Value
System_v4	Received	
RemoteScreenReceiver_v4	CurrentTime	14:48:33:23
RemoteScreenSender_v4	DayOfWeek	7
ioLogic_E1214_v4	DayOfMonth	25
PanasonicPT_Series	Month	11
EpsonProjector	Year	2017
DVS_Pronto		

*It has no commands and does not need a channel, because all the communication is internal.*

## Web Server

One way to create fast responsive web sites is to use the build in web server and WebSockets. This allows us to establish a stable, bidirectional connection between a web application and V-Control. The benefit of a bidirectional connection is, that our web application does not have to poll the V-Control web server to get status changes. As far as a status change of a device occurs, the information is sent to the web application. All we need is to write a handler for this status message and show the new status in our GUI.

In the example below a websocket is initialized

```
<!DOCTYPE html>
<!--
To change this license header, choose License Headers in Project
Properties.To change this template file, choose Tools |
Templatesand open the template in the editor.-->
<html>
  <head>
    <meta content="text/html; charset=UTF-8" http-
equiv="content-type">
    <title>V-Control Web Example</title>
    <meta name="viewport" content="width=device-width,
initial-scale=1.0, user-scalable=no">
    <link rel="stylesheet" type="text/css"
href="./js/libs/jquery-ui-1.10.4.custom.min.css">
    <link rel="stylesheet" type="text/css"
href="./js/libs/jquery-ui-1.10.4.custom.css">
    <link rel="stylesheet" type="text/css" href="main.css">
    <script src="./js/libs/jquery/jquery.js"></script>
    <script src="./js/libs/jquery/jquery-ui-
1.10.4.custom.min.js"></script>
    <script src="./js/libs/v-control.js"></script>
    <script>
      $(document).ready(function() {

//*****
      //Change the IP with the IP Address of your V-
Control system
      initWebSocket("ws://127.0.0.1:8080"); //use the
same port as on V-Control httpRemote (8080 here)

//*****
      });
```

For more information please use your favorite search engine and learn more about JavaScript and HTML (if necessary) There is also an example with V-Control 3. This will not work in the same way with V-Control4, but will be a good starting point to learn how to do. <https://v-control.com/touch-guis-with-websockets/>

## **Language / IDE of your Choice**

*Because V-Control uses an open API, you can use any language / IDE you familiar with and create graphical user interfaces. The API is explained here:  
Remote Protocol*

# Device Editor

Device Drivers are very flexible, and for that reason they are also very complex. In fact, creating device drivers is the most complex part in V-Control.

All available device drivers are stored as a template in a database (Devices.rsd). Once they're added to a project, a copy is stored in the project file (\*.vc4) too. The Device Editor is used to modify / create these drivers. To modify a driver in an existing project file, the Device Editor is launched via *Configure -> Edit Devices* or the *Device Edit* toolbar button. Now only devices in the current project are available for editing. This means also that all changes to the device driver concern only the current project. The device database with the templates stays untouched. To edit the device templates, the device editor is launched via *Configure -> Edit Device Templates*. In this case, the drivers in the current project stay untouched.

The screenshot shows the 'Device Editor' window. The top section, titled 'Driver', contains fields for device identification and configuration: ID (0), Device GUI (Standard), DP1 Name, DP2 Name, Device (dropdown), DP1 GUI (dropdown), DP1 MinMax, DP2 MinMax, Type, DP1 Default, DP2 Default, Manufacturer, DP1 Mask, DP2 Mask, Category (dropdown), Add Category button, Name (MyDevice), Change Category checkbox, and buttons for Add Device, Update Device, and Delete Device. A 'Variable Name' field and Add/Delete Variable buttons are also present. The bottom section, titled 'Commands', has tabs for 'Source' and 'HelpText'. It includes buttons for Add Cmd, Update Cmd, and Delete Cmd. A table with columns 'Pos.' and 'Name' is on the left. To the right are fields for Name, Position, Type, ACK Cmd (dropdown), Repeat (1=20ms) (0), and Timeout (0). Further right are fields for P1 Name, P1 GUI, P1 MinMax, P1 Default, P1 Mask, P2 Name, P2 GUI, P2 MinMax, P2 Default, P2 Mask, P3 Name, P3 GUI, P3 MinMax, P3 Default, P3 Mask, P4 Name, P4 GUI, P4 MinMax, P4 Default, P4 Mask, Ack in Hex, Ack Length, and buttons for To Hex, To ASCII, and Compile.

The Device Editor is split into two main sections. The upper part concerns all Device properties, the lower part contains all commands of a device. The image shows the Device Editor for editing devices that are part of the project, not the Device Templates.

## Parameter

Many commands sent to a device need parameter(s) to make sense. E.g. a CueUp command for a Player need a Timecode to tell the player where to go. An example for a parameter less command is the Play command. This instruction contains all the information that is needed for the driver, simply



turn the device in play mode. As these examples show, it is necessary to refer parameters to a command.

In V-Control, up to six parameters for each command are available. We distinguish between device parameters (DP1 and DP2) and command parameters (P1 - P4). Both parameter types are equivalent and used in the same way. Device parameters concern more the device itself. For example, some projectors can daisy chain the serial signal so that many projectors can use the same serial port. In this case all projectors in that chain get the same serial commands, so each projector need a unique address. This address is, from V-Control 's point of view, a parameter. Because this parameter concerns the device and not the command, we use it as device parameter. If an InputSelect command is sent to one of those projectors in the chain, two parameters are needed, one that addresses the device, and one that say the addressed device which input should be selected.

Another example for a device parameter is the Modbus TCP protocol. Some devices require their own Unit ID, even if they are only accessible under a specific IP address.

Devices	Var Name	Value
HSW_Drehscheiben_Mon	Received	&hC3&hB7...
PJLink	Status	OK
<b>ioLogik E1214</b>	K0Status	0
HSW Drehscheiben Monit...	K1Status	0
V7300_1	K2Status	0
V7300_2	K3Status	0
V7300_3	K4Status	0
V7300_4	K5Status	0
V7300_5	D0Status	0
V7300_6	D1Status	0
V7300_7	D2Status	0
V7300_8	D3Status	0
RemoteScreenRec	D4Status	0
RemoteScreenSender	D5Status	0
System_v4_1216		
VControlNode_1218		
OSC_1220		

Pos	Commands
030	<b>SetSingleRelay</b>
040	SetMultipleRelays

Unit ID: 255

RelayNb: 5

Value: OFF

Add Cmd ? Run Cmd

To enter a parameter, an parameter input field is needed. This could be a text field, a spin button or a drop down box. In the example above a spin button is used to enter the Unit ID (Unit ID is a Device Parameter in this case) and the RelayNb. A drop down box determines whether the relay should be switched on or off. The parameter input field is defined by five controls in the device editor. These are the same for Device Parameter and Command Parameter.

DP1 Name: <input style="width: 100%;" type="text"/> DP1 GUI: <span style="border: 1px solid black; padding: 2px;">Text</span> <small>▼</small> DP1 MinMax: <input style="width: 100%;" type="text"/> DP1 Default: <input style="width: 100%;" type="text"/> DP1 Mask: <input style="width: 100%;" type="text"/>	DP2 Name: <input style="width: 100%;" type="text"/> DP2 GUI: <span style="border: 1px solid black; padding: 2px;">Text</span> <small>▼</small> DP2 MinMax: <input style="width: 100%;" type="text"/> DP2 Default: <input style="width: 100%;" type="text"/> DP2 Mask: <input style="width: 100%;" type="text"/>	<div style="border: 1px solid black; padding: 5px; height: 40px;">         Name          Received          Power          RGBInput          VideoInput          DigitalInput       </div> <div style="display: flex; justify-content: space-between;"> <span>Variable Name:</span> <input style="width: 100%;" type="text"/> </div>
<input type="button" value="Add Device"/> <input type="button" value="Update Device"/> <input type="button" value="Delete Device"/>	<input type="button" value="Add Variable"/> <input type="button" value="Delete Variable"/>	

<div style="display: flex; justify-content: space-between;"> <div> <input style="width: 100%;" type="text"/>  <input style="width: 100%;" type="text"/>  <input style="width: 100%;" type="text"/> </div> <div>           ACK Cmd: <span style="border: 1px solid black; padding: 2px;"> </span> <small>▼</small>            Repeat (1=20ms): <input style="width: 100%;" type="text"/>            Timeout: <input style="width: 100%;" type="text" value="0"/> </div> </div> <div style="border: 1px solid black; height: 100px; margin-top: 10px;"></div>	<table style="width: 100%;"> <tr> <td style="width: 50%;">           P1 Name: <input style="width: 100%;" type="text"/>            P1 GUI: <span style="border: 1px solid black; padding: 2px;">Text</span> <small>▼</small>            P1 MinMax: <input style="width: 100%;" type="text"/>            P1 Default: <input style="width: 100%;" type="text"/>            P1 Mask: <input style="width: 100%;" type="text"/> </td> <td style="width: 50%;">           P2 Name: <input style="width: 100%;" type="text"/>            P2 GUI: <span style="border: 1px solid black; padding: 2px;">Text</span> <small>▼</small>            P2 MinMax: <input style="width: 100%;" type="text"/>            P2 Default: <input style="width: 100%;" type="text"/>            P2 Mask: <input style="width: 100%;" type="text"/> </td> </tr> <tr> <td>           P3 Name: <input style="width: 100%;" type="text"/>            P3 GUI: <span style="border: 1px solid black; padding: 2px;">Text</span> <small>▼</small>            P3 MinMax: <input style="width: 100%;" type="text"/>            P3 Default: <input style="width: 100%;" type="text"/>            P3 Mask: <input style="width: 100%;" type="text"/> </td> <td>           P4 Name: <input style="width: 100%;" type="text"/>            P4 GUI: <span style="border: 1px solid black; padding: 2px;">Text</span> <small>▼</small>            P4 MinMax: <input style="width: 100%;" type="text"/>            P4 Default: <input style="width: 100%;" type="text"/>            P4 Mask: <input style="width: 100%;" type="text"/> </td> </tr> </table> <div style="display: flex; justify-content: space-between; margin-top: 10px;"> <div>           ACK in Hex: <input style="width: 100%;" type="text"/>            Ack Length: <input style="width: 100%;" type="text"/> </div> <div style="text-align: right;"> <input type="button" value="To Hex"/>  <input type="button" value="To ASCII"/> </div> </div> <div style="text-align: right; margin-top: 10px;"> <input type="button" value="Compile"/> </div>	P1 Name: <input style="width: 100%;" type="text"/> P1 GUI: <span style="border: 1px solid black; padding: 2px;">Text</span> <small>▼</small> P1 MinMax: <input style="width: 100%;" type="text"/> P1 Default: <input style="width: 100%;" type="text"/> P1 Mask: <input style="width: 100%;" type="text"/>	P2 Name: <input style="width: 100%;" type="text"/> P2 GUI: <span style="border: 1px solid black; padding: 2px;">Text</span> <small>▼</small> P2 MinMax: <input style="width: 100%;" type="text"/> P2 Default: <input style="width: 100%;" type="text"/> P2 Mask: <input style="width: 100%;" type="text"/>	P3 Name: <input style="width: 100%;" type="text"/> P3 GUI: <span style="border: 1px solid black; padding: 2px;">Text</span> <small>▼</small> P3 MinMax: <input style="width: 100%;" type="text"/> P3 Default: <input style="width: 100%;" type="text"/> P3 Mask: <input style="width: 100%;" type="text"/>	P4 Name: <input style="width: 100%;" type="text"/> P4 GUI: <span style="border: 1px solid black; padding: 2px;">Text</span> <small>▼</small> P4 MinMax: <input style="width: 100%;" type="text"/> P4 Default: <input style="width: 100%;" type="text"/> P4 Mask: <input style="width: 100%;" type="text"/>
P1 Name: <input style="width: 100%;" type="text"/> P1 GUI: <span style="border: 1px solid black; padding: 2px;">Text</span> <small>▼</small> P1 MinMax: <input style="width: 100%;" type="text"/> P1 Default: <input style="width: 100%;" type="text"/> P1 Mask: <input style="width: 100%;" type="text"/>	P2 Name: <input style="width: 100%;" type="text"/> P2 GUI: <span style="border: 1px solid black; padding: 2px;">Text</span> <small>▼</small> P2 MinMax: <input style="width: 100%;" type="text"/> P2 Default: <input style="width: 100%;" type="text"/> P2 Mask: <input style="width: 100%;" type="text"/>				
P3 Name: <input style="width: 100%;" type="text"/> P3 GUI: <span style="border: 1px solid black; padding: 2px;">Text</span> <small>▼</small> P3 MinMax: <input style="width: 100%;" type="text"/> P3 Default: <input style="width: 100%;" type="text"/> P3 Mask: <input style="width: 100%;" type="text"/>	P4 Name: <input style="width: 100%;" type="text"/> P4 GUI: <span style="border: 1px solid black; padding: 2px;">Text</span> <small>▼</small> P4 MinMax: <input style="width: 100%;" type="text"/> P4 Default: <input style="width: 100%;" type="text"/> P4 Mask: <input style="width: 100%;" type="text"/>				

1. Name: The name of the parameter. This is just a label that tells the user what kind of parameter is needed.

2. GUI: The type of the input field. Three types are available.

- Spin Button: A field for numeric values
- Drop Down Box: A list of predefined values
- Textfield: An input field for all kind of parameters

3. MinMax:

- If the GUI type is spin button, then this field contains the minimum and maximum value, separated by a semicolon. If the youser should enter a value between 1 and 19, then 1;19 is entered here.
- If the GUI type is drop down box, then this field contain a semicolon separated list of all possible values. E.G. if the projector has a RGB, a Video and a S-Video input, the content of this field could be "RGB;VIDEO;S-VIDEO".
- If the GUI type is text field, then this field is inactive.

#### 4. Default:

- If the GUI type is spin button, then this field optionally contains the default numeric value that is used for the parameter. The default value must be in the range defined with the MinMax value.
- If the GUI type is drop down box, this field contains the list item selected by default. The value MUST be one of the semicolon separated values defined in the MinMax field.
- If the GUI type is text field, then this field contains the default value for the text field.

#### 5. Mask:

- Inactive if GUI type is spin button
- Inactive if GUI type is drop down box
- If the GUI type is text field, an optional mask for the field is defined here.

Mask Character	Description
#	Any single digit placeholder. The user can type only a digit character in this position.
.	Decimal placeholder. The decimal placeholder that is actually used is specified in the user's International settings. The character is treated as a literal (formatting) character for masking purposes.
,	Thousands separator. The thousands separator that is actually used is specified in the user's International settings. The character is treated as a literal (formatting) character for masking purposes.
:	Time separator. The time separator that is actually used is specified in the user's International settings. The character is treated as a literal (formatting) character for masking purposes.
/	Date separator. The date separator that is actually used is specified in the user's International settings. The character is treated as a literal (formatting) character for masking purposes.
\	Mask escape character. Treat the next character in the mask as a literal. The

	escape character enables you to use the '#', '&', 'A', '?' (and so on) characters in the mask. The escaped character is treated as a literal (formatting) character.
&	Character placeholder. Valid values are the ASCII characters 32-126 and the non-ASCII characters 128-255.
>	Convert all the characters that follow to uppercase. Upper casing works beyond the ASCII range where appropriate, e.g., ü becomes Ü.
<	Convert all the characters that follow to lowercase. Lower casing works beyond the ASCII range where appropriate, e.g., Ü becomes ü.
A	Alphanumeric character placeholder, where entry is mandatory. For example, the spec "AAA" specifies three alphabetic characters.
a	Alphanumeric character placeholder, where entry is optional.
9	Digit placeholder where entry is optional.
C	Character or space placeholder, where entry is optional. It operates like the '&' placeholder.
?	Alphabetic placeholder.
Any literal	All other symbols are displayed as literals for formatting purposes.
~	Reserved for future use. If you use "~" it will trigger an exception error. Use \~ instead.

# Command Types

Comands Source Help text

Add Cmd Update Cmd Delete Cmd

Pos.	Name
------	------

Name:

Position:

Type:

ACK Cmd:

Repeat (1=20ms):

Timeout:

P1 Name:

P1 GUI:

P1 MinMax:

P1 Default:

P1 Mask:

P2 Name:

P2 GUI:

P2 MinMax:

P2 Default:

P2 Mask:

P3 Name:

P3 GUI:

P3 MinMax:

P3 Default:

P3 Mask:

P4 Name:

P4 GUI:

P4 MinMax:

P4 Default:

P4 Mask:

Ack in Hex:

Ack Length:

To Hex To ASCII Compile


A device driver as 4 different types of commands:

1. **Command:** This is a command that appears in the command list. These are the commands that the user uses to control the device.
2. **Ack Command:** An Ack(nowledge) command is a command that is executed after a command or timer command was send. These commands are used to process the data returned from the device.
3. **Monitor Command:** This is a command that is executed periodically. It is used to request the status of a device. An Ack Command is used to process the result and fill device variables with information.
4. **Event:** To be exact, an event is not a command. An event occurs if a device send information to a driver without being requested before. This Data is handled here in a very similar way then in Ack Commands.

## Create New Driver

In the following example, we create a new driver for the Adtec SOLOIST 2 MPEG player. I use this old fashioned device because we see all aspects of device drivers here. To start this job, it is necessary to have the protocol provided by the manufacturer and study it. The protocol describes the RS232 settings (baudrate, start bits, stop bits, parity) and the control cable pin assignment as well as the commands the device understand. The default RS232 parameters are 38400 baud, 8 data bits, 1 stop bit and no parity, so we need to create a channel with these parameters. In this example we call it "soloist".

There is no device using a protocol that is similar to Adtec's SOLOIST 2, so we load the Generic Device from the I/O category ( see Device Setup ) and assign the channel "soloist" to this device. Then the project is saved as e.g. soloist\_test.vc4.



## Simple Commands

To start we need to launch the device editor via main menu *Configure -> Edit Devices* and select the device *GenericDevice\_1*.

The two commands *OnData* and *SendString* are not used and can be deleted. To do that click on the command and then click on *Delete Cmd* (see screenshot)

File  
Driver

ID: 0      Device GUI:      DP1 Name:      DP2 Name:

Device: Generic\_1      Standard      DP1 GUI: Text      DP2 GUI:

Type: Generic      DP1 MinMax:      DP2 MinMax:

Manufacturer: VMAN      DP1 Default:      DP2 Default:

Category: I/O      Add Category      DP1 Mask:      DP2 Mask:

Name: Generic\_1      ☐ Change Category      Add Device      Update Device

Commands    Source    HelpText

Add Cmd    Update Cmd    Delete Cmd

Pos.	Name
050	SendText
051	SendBinary

Name: SendText      ACK Cmd:      Repeat (1=20ms): 0      Timeout: 0

Position: 50      Type: Command

```

P2Default = P1
P2Default = P2
if P2 = "None" then P2 = ""
if P2 = "CR" then P2 = chr(13)
if P2 = "LF" then P2 = chr(10)
if P2 = "CR+LF" then P2 = chr(13) + chr(10)
ScriptResult = P1 + P2

```

Each command for the SOLOIST 2 player need at least one parameter - the name of the device. The "\*" character is used as a universal name and every SOLOIST accept this sign as his name. Because the SOLOIST name concern the device and not the command it is implemented as device parameter. In the field *DP1 Name* enter "Name" as identifier and "\*" in the field *DP1 Default*. To add this parameter to the device click *Update Device*.

File  
Driver

ID: 0      Device GUI:      DP1 Name: Name      DP2 Name:

Device: Generic\_1      Standard      DP1 GUI: Text      DP2 GUI: Text

Type: Generic      DP1 MinMax:      DP2 MinMax:

Manufacturer: VMAN      DP1 Default: \*      DP2 Default:

Category: I/O      Add Category      DP1 Mask:      DP2 Mask:

Name: Generic\_1      ☐ Change Category      Add Device      Update Device      Delete Device

The first command we implement is the STOP command. The command string looks like this: "\* STOP" + Chr(13). As feedback (Acknowledge) the SOLOIST 2

send "OK"+ CR+LF+CR+LF. CR means Carriage Return and LF Line Feed. CR is the ASCII Coder 13, or 0D in hexadecimal. LF is 10 or 0A in hexadecimal.

The screenshot shows the 'Commands' tab in the V-Control software. It features a table of commands with columns for 'Pos.' and 'Name'. The first entry is '010 Stop'. To the right of the table are fields for editing a command: 'Name' (Stop), 'Position' (10), 'Type' (Command), 'ACK Cmd' (dropdown), 'Repeat (1=20ms)' (0), and 'Timeout' (500). Below these is a large text area for 'Scriptresult' containing the code `DP1+" STOP"+ chrB(13)`. To the right of the script area are fields for parameters P1 through P4, each with a 'Name', 'GUI' (dropdown), 'MinMax', 'Default', and 'Mask' field. At the bottom right, there are fields for 'Ack in Hex' (0D0A), 'Ack Length' (0), and buttons for 'To Hex', 'To ASCII', and 'Compile'.

To implement the command follow the instructions in the screenshot.

- Command Name: Because the command is a Stop command the name is obvious. In V-Control command names are used as function calls. Therefore names like GoTo, Exit or Sub are illegal, because they are Basic functions respectively reserved keywords. If one of those reserved words is used, the compiler generates a compiler error while compiling the script.
- The number in the *Position* field serves as sort criterion in the command list.
- The Type determines the type of command (see **Command Types**)
- The source code of the command. The variable ScriptResult has a special job. It contains the command string, that is sent via channel to the device. This means that the variable ScriptResult must contain a string that causes a Stop command for the Adtec player. The line `ScriptResult = DP1 + " STOP" + ChrB(13)` assigns parameter DP1 to ScriptResult. DP1 is the first of two available device parameter and contains in this case the name of the SOLOIST. Totally up to six parameter (DP1,DP2,P1,P2,P3,P4) are available, but this time we use only DP1. Then a space character followed by STOP (" STOP") is added. The ChrB function converts an Integer value to ASCII code. The SOLOIST 2 expect a Carriage Return (ASCII code 13) as terminating character which is added by the ChrB function. Now the command string is complete.
- The command timeout in milliseconds. If there is no response (Acknowledge) within this time, a Timeout message is created.

The Timeout leads to the question, how V-Control knows if, respectively when, an Acknowledge is present. That tells the field Ack in Hex: Here the expected response is entered. The screenshot below shows that the 0D0A is expected.



Ack in Hex:

Ack Length:

As Ack String, only Hex code is accepted. So you need to convert everything to Hex. If you enter text in the *Ack in Hex* field and press the button *To Hex*, the text converts ASCII String to hex code.

But the SOLOIST 2 not only send 0D0A as Acknowledge. The complete string is OK0D0A0D0A. Well, we don't care about that. If we received 0A0D then we know that the message was received and processed by the Soloist.

The first command is complete. A click on the button *Add Cmd* saves the command. Because V-Control compiles the script, we have to click the *Compile* button. If there is an error, the compiler posts a compiler error, otherwise the device is usable now. To do that, close the Device Editor and select the Device GenericDevice\_1 again (see screenshot below). The Stop command now appears in the command list. The device parameter Name has the "\*" character as default value. Alternatively we can use the real SOLOIST 2 name, e.g. "SOLOIST".

If the command is working it is recommended to save the project. Until now, the driver exists only in the project file ("soloist\_test.vc4" in this example), and this file contains all the work we did. If the driver is complete, we will export it and then import it to the device database. To complete the driver we start the Device Editor via main menu Configure -> Edit Devices again. The table below shows the remaining simple commands for the SOLOIST 2 player. Proceed in the same way as we did with the Stop command.

Name	Position	Type	Timeout	Script	Ack in Hex
Play	11	Comands	500	Scriptresult = DP1 + "PLAY" + chrB(13)	0D0A
Next_Clip	20	Comands	500	Scriptresult = DP1 + "NEXT" + chrB(13)	0D0A
Prev_Clip	21	Comands	500	Scriptresult = DP1 + "PREVIOUS" + chrB(13)	0D0A
Still	22	Comands	500	Scriptresult = DP1 + "PAUSE" + chrB(13)	0D0A
Rewind	23	Comands	500	Scriptresult = DP1 + "REWIND" +	0D0A

				chrB(13)	
--	--	--	--	----------	--

The result should look like this:

Finally click the *Compile* button and test the driver.

Now the general conditions to control the device are created. As pointed out in the SOLOIST 2 protocol, the general command format for the device is:

<NAME><SEP><COMMAND><SEP>[ARGUMENT(S)][SEP]<CR>

Parameters in angle brackets <> are mandatory Parameters in square bracket [] are optional

- NAME: SOLOIST Name, up to 20 characters. The SOLOIST 2 is capable to daisy chain the RS232 signal to other SOLOIST players. Thus it is necessary to have a unique ID for each device which is represented by the name. The "\*" symbol addresses all player, whatever the name of the device is.
- SEP: Separator character, SPACE (" "), comma(",") or semicolon(";;")
- COMMAND: ASCII string for the command, e.g. "PLAY", "STOP" or "PLAYSPOT"
- ARGUMENTS: some commands need arguments (parameter) to make sense. E.g. the PLAYSPOT command need the clip that has to be played as parameter.
- CR: Carriage Return (Enter Key, ASCII Code 13)

Respecting the above instructions, the command string for a simple PLAY command sent to a device named "SOLOIST" looks like this:

"SOLOIST PLAY" + chr(13)

## Complex Commands

In this chapter the SOLOIST 2 driver is enhanced with a couple of more complex commands. These commands need one or more parameters. In the chapter before, we used the Device Parameter 1 (DP1) to address the SOLOIST (DP1 contain the name of the SOLOIST). The following four commands use more then one parameter. Additionally the three types of input fields (Text

Field, Spin Button and Drop Down Box) are introduced.

The first new command is the “SetName” command. With this command we can change the SOLOIST's ID. Start the Device Editor again (menu *Configure -> Edit Device...*) and select the device GenericDevice\_1.

The screenshot shows the 'Device Editor' window with the 'Commands' tab selected. On the left, a list of commands is shown, with 'SetName' at position 020. The main area displays the configuration for 'SetName':

- Name: SetName
- Position: 20
- Type: Command
- Scriptresult: `DP1+" NAME " + P1 + chrB(13)`
- ACK Cmd: (dropdown)
- Repeat (1=20ms): 0
- Timeout: 500

On the right, there are four parameter sets (P1, P2, P3, P4) with fields for Name, GUI, MinMax, Default, and Mask. P1 Name is 'Name', P1 GUI is 'Text'. At the bottom, there are fields for 'Ack in Hex' (0D0A), 'Ack Length' (0), and buttons for 'To Hex', 'To ASCII', and 'Compile'.

The creation of this command is very similar to the commands described in the chapter before. The difference is that we use one more parameter (P1). The field *P1Name* shows the parameters name. Because the command shall change the name we call the parameter “SetName”. *P1 GUI* stays at Text, because it makes sense to use a text field to enter a new name. In difference to DP1 we don't use a default value.

Crucially again is the line `Scriptresult = DP1+" NAME " + P1 + chrB(13)`. As before, DP1 contains the current ID (name) of the SOLOIST player. Then the command string “ NAME ”, with leading and succeeding space character is added. P1 contains the new name for the SOLOIST and ChrB(13) is for the carriage return (ASCII code 13) termination character. To save the new command click *Add Cmd* or *Update Cmd* (if the command was edited) followed by *Compile*.

The next command is *SetErrorLimit*, which determines how often the player try to read from hard disk, before playing interrupts. Valid parameter is a number between 0 and 1000. To enter this parameter we want to use a Spin Button. The Device Editor now looks like this:

The screenshot shows the 'Device Editor' window with the 'Commands' tab selected. On the left, a list of commands is shown, with 'SetErrorLimit' at position 030. The main area displays the configuration for 'SetErrorLimit':

- Name: SetErrorLimit
- Position: 30
- Type: Command
- Scriptresult: `DP1+" ERRORLIMIT " + P1 + chrB(13)`
- ACK Cmd: (dropdown)
- Repeat (1=20ms): 0
- Timeout: 500

On the right, there are four parameter sets (P1, P2, P3, P4) with fields for Name, GUI, MinMax, Default, and Mask. P1 Name is 'Error Limit', P1 GUI is 'Spin Button', P1 MinMax is '0;1000', and P1 Default is '0'. At the bottom, there are fields for 'Ack in Hex' (0D0A), 'Ack Length' (0), and buttons for 'To Hex', 'To ASCII', and 'Compile'.

*P1 Name* contains the designation of the parameter as usual ("Error Limit"), but *P1 GUI* is set to Spin Button. *P1 MinMax* contain, separated by semicolon, the minimum and maximum numeric value that P1 might have. As default value 0 is selected, because usually there should be no reading error. Comparing to the previous command, the script is the same except that we replace " NAME " by " ERRORLIMIT ". Don't forget to click *Add Cmd* or *Update Cmd* followed by *Compile*.

The StartUp command determines how the SOLOIST player behaves on Power On. If StartUp = On, the player starts playing after power on, if StartUp = Off the player do nothing. There are only two possible values as parameter, "On" and "Off", so we use a Drop Down Box as input field.

Comands Source HelpText

Pos.	Name	Name:	Position:	Type:	ACK Cmd:	Repeat (1=20ms):	Timeout:	P1 Name:	P1 GUI:	P1 MinMax:	P1 Default:	P1 Mask:	P2 Name:	P2 GUI:	P2 MinMax:	P2 Default:	P2 Mask:	P3 Name:	P3 GUI:	P3 MinMax:	P3 Default:	P3 Mask:	P4 Name:	P4 GUI:	P4 MinMax:	P4 Default:	P4 Mask:	AcK in Hex:	AcK Length:	To Hex	To ASCII	Compile
010	Stop																															
011	Play																															
012	Next_Clip																															
013	Prev_Clip																															
014	Pause																															
015	Rewind																															
020	SetName																															
030	SetErrorLimit																															
030	SetStartup	SetStartup	30	Command		0	500		Drop Down	On;Off				Text					Text				Text				0D0A	0				

Scriptresult = DP1+"STARTUP " + P1 + chrB(13)

*P1 Name* contains the designation of the parameter as usual ("Startup"), but *P1 GUI* is set to Drop Down. *P1 MinMax* contain, separated by semicolon, the possible values, that P1 might have. Comparing to the previous command, the script is the same except that we replace " ERRORLIMIT " by " STARTUP ". Don't forget to click *Add Cmd* or *Update Cmd* followed by *Compile*.

The last command is the CueUp command. This command lets the SOLOIST jump to a position in the currently loaded clip. The position is entered as timecode (HH-MM-SS-FF) which addresses an absolute position in the clip. But the SOLOIST also knows relative positions. E.g. "+ 00-01-02-00" jumps forward one minute and two seconds from the current position. "- 00-01-02-00" jumps one minute and two seconds back. So we need three parameters (Soloist Name, absolute or relative position and the position as time code).

Comands Source HelpText

Add Cmd Update Cmd Delete Cmd

Pos.	Name	Name:	ACK Cmd:
010	Stop	CueUp	
011	Play	Position: 40	Repeat (1=20ms): 0
012	Next_Clip	Type: Command	Timeout: 500
013	Prev_Clip		
014	Pause		
015	Rewind		
020	SetName		
030	SetErrorLimit		
030	SetStartup		
040	CueUp		

```
//Replace all "-" characters In Parameter2 With ":"
P2 = ReplaceAll(P2,"-",":")

If P1 = "Absolute" Then ScriptResult = DP1 + " INDEX " + P2 + Chr(13)
If P1 = "+" Then ScriptResult = DP1 + " INDEX + " + P2 + Chr(13)
If P1 = "-" Then ScriptResult = DP1 + " INDEX - " + P2 + Chr(13)
```

P1 Name: Mode P2 Name: Timecode

P1 GUI: Drop Down P2 GUI: Text

P1 MinMax: Absolute;+;- P2 MinMax: ##-##-##

P1 Default: Absolute P2 Default:

P1 Mask: P2 Mask:

P3 Name: P4 Name:

P3 GUI: Text P4 GUI: Text

P3 MinMax: P4 MinMax:

P3 Default: P4 Default:

P3 Mask: P4 Mask:

AcK in Hex: 0D0A To Hex

Ack Length: 0 To ASCII Compile

The parameter *P1* determines the mode (absolute, relative +, relative -), and is implemented as Drop Down Box. The default value is "Absolute", because this is the most often wanted mode. *P2* is the parameter for the time code and implemented as text field. *P2 Mask* set the input mask for this parameter. In this case, only numeric values are accepted, separated by "-" character. We can not use the ":" as separator in a mask, because it is used for time formats (HH:MM:SS) and not for Time code (HH-MM-FF-SS).

This time, the script is a little more complex:

```
//Replace all "-" characters In Parameter2 With ":"
P2 = ReplaceAll(P2,"-",":")
```

```
If P1 = "Absolute" Then ScriptResult = DP1 + " INDEX " + P2 + Chr(13)
If P1 = "+" Then ScriptResult = DP1 + " INDEX + " + P2 + Chr(13)
If P1 = "-" Then ScriptResult = DP1 + " INDEX - " + P2 + Chr(13)
```

The SOLOIST expects the time code in the format "HH:MM:SS:FF", with ":" as separator and not "-". *P2* uses "-" as separator, so we have to replace any "-" sign by a ":". This is what `P2 = ReplaceAll(P2,"-",":")` does. Then we compare the value of *P1* with "Absolute". If true (*P1* = "Absolute") then no "+" or "-" sign is leading the time code and for the SOLOIST this is an absolute value. Don't forget to click *Add Cmd* or *Update Cmd* followed by *Compile*.

## Hep Text

Every device driver can have a help text. The text is for the user to give him some hints or necessary information to use the driver and / or the device. It is often used to describe the RS232 properties like baud rate, data bits, parity etc. or the pin assignment for the control cable.

Comands Source Helptext

Default RS232 Parameter:

Baud: 38400  
DataBits: 8  
StopBits:1  
Parity: None

Control Calble Pinout:

PC (DB 25 Female)    Soloist (RJ11)

1	-----	4
2	-----	5
3	-----	2
7	-----	3

PC (DB 9 Female)    Soloist (RJ11)

2	-----	2
3	-----	5
5	-----	3

The Command GetInventory should be executed each time the content of the Soloist disc has changed. This command adds all available Clips on the Soloist to the Commands PlaySpot and CueSpot.

If the help text is complete, the button Update Device saves the text in the database. In the Device GUI it is now retrievable via Help button ?.

Device Events

Commands Setup

Pos

Commands

010 Stop

011 Play

012 Next\_Clip

013 Prev\_Clip

014 Pause

015 Rewind

020 SetName

030 SetErrorLimit

030 SetStartup

040 CueUp

Name \*

Add Cmd

?

Run Cmd

0 Pending Acks 0

Device Help

Default RS232 Parameter:

Baud: 38400  
DataBits: 8  
StopBits:1  
Parity: None

Control Calble Pinout:

PC (DB 25 Female)    Soloist (RJ11)

1	-----	4
2	-----	5
3	-----	2
7	-----	3

PC (DB 9 Female)    Soloist (RJ11)

2	-----	2
3	-----	5
5	-----	3

The Command GetInventory should be executed each time the content of the Soloist disc has changed. This command adds all available Clips on the Soloist to the Commands PlaySpot and CueSpot.

## Monitor and Acknowledge Comands

In all our examples we used the ACK string (ACK in Hex:). If the attached device send this string as response, we know that the command was understood and executed (usually, some devices send two acknowledges, one if the command was valid and one when execution is finished). If the expected string is not received in the time determined by Timeout, a Timeout error occurs. But there are acknowledges that need to be processed further.

For a player, V-Control should always know the playback position. The Soloist has a command "TIMECODE", which returns the current position as timecode. We want to have this useful information in a device variable. We need a combination of Monitor command and Ack command to do this.

## Monitor Commands

A monitor command is a command that is executed periodically. It is used to request the status of a device. This can be a projectors lamp hours or power status, or in the following example the timcode position of a player.

To create a *Monitor Command* select it in the commands type field (drop down box).

The screenshot shows the 'Monitor Command' configuration window. On the left, a list of commands is shown, with '100 GetPosition' selected. The central area contains fields for 'Name' (GetPosition), 'Position' (100), 'Type' (Monitor Command), 'ACK Cmd' (a dropdown), 'Repeat (1=20ms)' (1), and 'Timeout' (500). Below these is a script editor containing the text: `Scriptresult = DP1 + "TIMECODE" + chr(13)`. The right-hand panel contains fields for P1 Name, P1 GUI, P1 MinMax, P1 Default, P1 Mask, P2 Name, P2 GUI, P2 MinMax, P2 Default, P2 Mask, P3 Name, P3 GUI, P3 MinMax, P3 Default, P3 Mask, P4 Name, P4 GUI, P4 MinMax, P4 Default, P4 Mask, 'Ack in Hex' (0D0A), 'Ack Length' (0), and buttons for 'To Hex', 'To ASCII', and 'Compile'.

The fields *Timeout* and *Ack in Hex* are used in the same way then before. Two things are new:

1. All command parameters are disabled. This is because this command is started by a timer. There is no user interaction when this command executes, so there is no chance to modify any parameters. But we can use the device parameters default values. In this case this is necessary, because we need the Soloist name for the command string.
2. A new field *Repeat* is enabled. Here we determine how often this command is executed. Values entered here can be between 1 and 3000. To determine how often this command executes multiply this value with 20ms. So 1 means this command is executed every 20ms (Milliseconds), 5 means every 100 ms.

It is important to know that there is only one timer per device. If you have two Monitor Commands, both using 1 as Repeat value, they are not fired every 20ms. In this case they are fired every 40ms (first 20ms slot command 1, second 20 ms slot command 2).

If you want to monitor i.e. a projectors lamp hours, input channel and power state, it does not make sense to fire these request very fast. Usually approx. 1 second is enough. One Second means a Repeat value of 50.


For the timecode position it makes sense to request it very fast, so we use 1 as repeat value here.

The command is complete, whats missing is processing the result and store it in a device variable. This is done by an *Ack Command*. The Ack Command is selected in the *Ack Cmd* drop down box. Because we do not have the command right now we need to create it and assign the Ack command to the GetPosition

command later.


## Ack(nowledge) Commands

The result of the GetPosition command has to be stored in a device variable. So the first step is to create one.



Enter the variable name in the *Variable Name* field and click the *Add Variable* button.

Next, create a new command as shown below.



Here we have a quite complex script to fetch the timecode from the Soloist returning message. This is because the soloist returns the timecode in the format `OK<CR><0A> H:MM:SS.FF<CR><0A>`, but we need `HH-MM-SS-FF`

OK, let's go through the lines:

Here we declare variables we need, all of type string in this case.

```
dim TC,HH,MM,SS,FF,tmp as string
```

The variable `IOResult` is permanently available and does not have to be declared. The Answer from the Soloist is stored here. If you don't know how `NthField` works please read the `NthField` documentation in the Compiler section.

The content of `IOResult` is `OK<CR><0A> H:MM:SS.FF<CR><0A>`, so we fetch the right part of the first `<CR>`

```
tmp = NthField(IOResult,chr(13),2)
```

now `tmp` has the content `<0A> H:MM:SS.FF`. Next we grab the Hours



```
HH = NthField(tmp,":",1)
```

HH is now <0A> H

then we grab Minutes and Seconds

```
MM = NthField(tmp,":",2)
```

```
SS = NthField(tmp,":",3)
```

Because the Frame delimiter is ".", we grab the frames by

```
FF = NthField(tmp,".",2)
```

Now get the Hours

```
HH = mid(HH,3)
```

HH = H now (one digit hours)

Make HH as two digit with preceding "0"

```
if len(HH) < 2 then HH = "0" + HH
```

Build the Timecode String

```
TC = HH+"- "+MM+"- "+SS+"- "+FF
```

Set the Device Variable

```
SetDeviceVar("Position",TC)
```

Now we assign this Command as Ack Command for the GetPosition command. Select the GetPosition command, and use the drop down box *Ack Cmd* to select *AckGetPosition*.

The screenshot shows the SOLOIST software interface with the 'Commands' tab selected. On the left, a list of commands is shown, with 'GetPosition' at position 100 highlighted. In the center, the 'Update Cmd' panel is active, showing the command name 'GetPosition', position '100', and type 'Monitor Command'. The script field contains 'Scriptresult = DP1 + " TIMECODE" + chr(13)'. The 'ACK Cmd' dropdown menu is open, showing a list of commands with 'AckGetPosition' selected at the bottom. On the right, there are configuration fields for four parameters (P1, P2, P3, P4), including Name, GUI, MinMax, Default, and Mask. At the bottom right, there are fields for 'Ack in Hex' (set to '0D0A'), 'Ack Length' (set to '0'), and buttons for 'To Hex', 'To ASCII', and 'Compile'.

## Automatic Parameters

This example shows how to automatic set the MinMax range of parameters. The SOLOIST knows the commands CUESPOT and PLAYSPOT, both need the name of the spot (clip) as parameter. It is of course possible to proceed in the same way than e.g. with the SetName command, and implement a text field that contains the clip name. But the SOLOIST also knows the command INVENTORY, which returns a list of all available clips on the machine. This leads to a more comfortable way to select a clip. We use the INVENTORY command to get all available clips, and then we put this list in the MinMax definition of

the CUESPOT and PLAYSPOT command. This presents the end user a picklist, and there is no need to type the clip names (and make mistakes).

To start with the example we create the CUESPOT command as shown below:

Comands Source Helptext

Add Cmd		Update Cmd		Delete Cmd	
Pos.	Name	Name:	CueSpot	ACK Cmd:	
010	Stop	Position:	45	Repeat (1=20ms):	0
011	Play	Type:	Command	Timeout:	500
012	Next_Clip	Scriptresult = DP1 + " CUESPOT " + "" + P1 + "" + chr(13)			
013	Prev_Clip				
014	Pause				
015	Rewind				
020	SetName				
030	SetErrorLimit				
030	SetStartup				
040	CueUp				
100	GetPosition				
101	AckGetPosition				

P1 Name:	ClipName	P2 Name:	
P1 GUI:	Drop Down	P2 GUI:	Text
P1 MinMax:		P2 MinMax:	
P1 Default:		P2 Default:	
P1 Mask:		P2 Mask:	
P3 Name:		P4 Name:	
P3 GUI:	Text	P4 GUI:	Text
P3 MinMax:		P4 MinMax:	
P3 Default:		P4 Default:	
P3 Mask:		P4 Mask:	
Ack in Hex:	0D0A	To Hex	
Ack Length:		To ASCII	
		Compile	

The script is only one line:

```
ScriptResult = DP1 + " CUESPOT " + "" + P1 + "" + Chr(13)
```

Respecting the SOLOIST protocol, the spot name has to be in quotation marks. The four quotation marks (""""") before and after P1 do this job. P1 GUI is a Drop Down list that contains a list of available clips. But at this time we don't know how many clips are present on the SOLOIST player, so it stays empty.

Then we create the command PLAYSPOT in the same way

```
ScriptResult = DP1 + " PLAYSPOT " + "" + P1 + "" + Chr(13)
```

Now we have two new commands, but until now they are not useful because we can't select a clip name as parameter.

To get all available clips we create the command "GetInventory". His job is to receive the clip list and fill the MinMax definition of PlaySpot and CueSpot commands. The GetInventory command is looks like this:

Comands Source Helptext

Add Cmd		Update Cmd		Delete Cmd	
Pos.	Name	Name:	GetInventory	ACK Cmd:	
010	Stop	Position:	43	Repeat (1=20ms):	0
011	Play	Type:	Command	Timeout:	500
012	Next_Clip	Scriptresult = DP1 + " INVENTORY " + chr(13)			
013	Prev_Clip				
014	Pause				
015	Rewind				
020	SetName				
030	SetErrorLimit				
030	SetStartup				
040	CueUp				
043	GetInventory				
044	CueSpot				
046	PlaySpot				
100	GetPosition				
101	AckGetPosition				

P1 Name:		P2 Name:	
P1 GUI:	Text	P2 GUI:	Text
P1 MinMax:		P2 MinMax:	
P1 Default:		P2 Default:	
P1 Mask:		P2 Mask:	
P3 Name:		P4 Name:	
P3 GUI:	Text	P4 GUI:	Text
P3 MinMax:		P4 MinMax:	
P3 Default:		P4 Default:	
P3 Mask:		P4 Mask:	
Ack in Hex:	0D0A	To Hex	
Ack Length:	0	To ASCII	
		Compile	

The GetInventory command does not fill the MinMax definitions. The command only tells the SOLOIST that the inventory list is requested. To read the list and fill the MinMax definitions, we use an acknowledge command, in this case

## ACK\_GetInventory.

Commands [Source](#) [HelpText](#)

Pos.	Name	Name:	Position:	Type:	ACK Cmd:	Repeat (1=20ms):	Timeout:
010	Stop	Ack_GetInventory	47	Ack Command		0	0
011	Play						
012	Next_Clip						
013	Prev_Clip						
014	Pause						
015	Rewind						
020	SetName						
030	SetErrorLimit						
030	SetStartup						
040	CueUp						
043	GetInventory						
044	CueSpot						
046	PlaySpot						
047	Ack_GetInventory						
100	GetPosition						
101	AckGetPosition						

```

dim i as integer
dim tmp, res as string
res = ""
for i = 1 to CountFields(IOResult,chr(13))
    //Dont use the first row and last two Rows
    if (i > 1) and (i < CountFields(IOResult,chr(13)) - 1) then
        tmp = NthField(IOResult,chr(13),i)
        //Delete first character because its trash
        tmp = mid(tmp,2)
        res = res + NthField(tmp," ",1) + ";"
    end
next
//Delete last ";"
res = left(res,len(res)-1)
ChangeCMD_MinMax("CueSpot","P1",res)
ChangeCMD_MinMax("PlaySpot","P1",res)

```

P1 Name:  P2 Name:

P1 GUI:  P2 GUI:

P1 MinMax:  P2 MinMax:

P1 Default:  P2 Default:

P1 Mask:  P2 Mask:

P3 Name:  P4 Name:

P3 GUI:  P4 GUI:

P3 MinMax:  P4 MinMax:

P3 Default:  P4 Default:

P3 Mask:  P4 Mask:

Ack in Hex:  To Hex

Ack Length:  To ASCII

The script is quite complex, so here some explanations:

Dim i As Integer

Dim tmp, res As String

res = ""

For i = 1 To CountFields(IOResult,Chr(13))

    //Dont use the first row And last two Rows

    If (i > 1) And (i < CountFields(IOResult,Chr(13)) - 1) Then

        tmp = NthField(IOResult,Chr(13),i)

        //Delete first character because it's trash

        tmp = Mid(tmp,2)

        res = res + NthField(tmp," ",1) + ";"

    End

Next

//Delete last ";"

res = Left(res,Len(res)-1)

//Replace current MinMax Value with res

ChangeCMD\_MinMax("CueSpot","P1",res)

ChangeCMD\_MinMax("PlaySpot","P1",res)

Line 1 declares i as Integer variable. It is used in the For .. Next loop as counter. Tmp is used as temporary variable and res is used to hold the new MinMax list. The function CountFields(IOResult,Chr(13)) tells how many lines (every line is terminated by chr(13)) in IOResult. The For .. Next loop is processed as many times, as chr(13) codes present in IOResult. The first line and the two last lines of IOResult don't contain any valid information, that's why the If .. Then statement present. The statement tmp = NthField(IOResult,Chr(13),i) assigns content of the i'st line to tmp. Then the content of tmp is added to res, followed by a semicolon.

Now we have to change the GetInventory command and tell it to use the acknowledge command.

Comands Source HelpText

Add Cmd Update Cmd Delete Cmd

Pos.	Name
010	Stop
011	Play
012	Next_Clip
013	Prev_Clip
014	Pause
015	Rewind
020	SetName
030	SetErrorLimit
030	SetStartup
040	CueUp
043	GetInventory
044	CueSpot
046	PlaySpot
047	Ack_GetInventory
100	GetPosition
101	AckGetPosition

Name: GetInventory  
Position: 43  
Type: Command

Scriptresult = DP1 + " INVENTORY" + chr(13)

ACK Cmd: **Ack\_GetInventory**

Repeat (1=20ms):  
Timeout:

P1 Name:   
P1 GUI: Text  
P1 MinMax:   
P1 Default:   
P1 Mask:   
P3 Name:   
P3 GUI: Text  
P3 MinMax:   
P3 Default:   
P3 Mask:

P2 Name:   
P2 GUI: Text  
P2 MinMax:   
P2 Default:   
P4 Name:   
P4 GUI: Text  
P4 MinMax:   
P4 Default:   
P4 Mask:

Ack in Hex: 0D0A To Hex  
Ack Length: 0 To ASCII Compile

Set Ack Cmd to "ACK\_GetInventory" (Update Cmd and Compile)

## Events

From a device drivers point of view, an event is a message received from a device without requesting it before.

In this example I use a weather station that sends Wind Speed, Temperature and Humidity every second. The format of the string is 4 digit wind speed, 5 digit temperature and two digit Humidity, all packed in one string.

12,323,5087 means 12,3 km/h wind speed, 23,50°C and 87% Humidity. There is no termination character, but we have a defined length (11 characters).

First we need 3 device variables to store the received data

Name

Received  
WindSpeed  
Temperature  
Humidity

Variable Name: Humidity

Add Variable Delete Variable

Then we need a new command of type *Event*. Here we use the *ACK Length* field to determine the amount of data that we need to process the event. If the Channel, that is associated with the device receives the data, it will look to the *Ack in Hex* and */* or *Ack Length* field. If one of them matches then the data is send to the device and the event is processed.

Comands Source HelpText

Add Cmd
Update Cmd
Delete Cmd

Pos.	Name
010	onData

Name: 
ACK Cmd:

Position: 
Repeat (1=20ms):

Type: 
Timeout:

```

dim s as string

//get the Wind Speed
s = mid(IOResult,1,4)
SetDeviceVar("WindSpeed",s)

//get the Temperature
s = mid(IOResult,5,5)
SetDeviceVar("Temperature",s)

//get the Humidity
s = mid(IOResult,10,2)
SetDeviceVar("Humidity",s)

```

## Export Device Driver

To transfer a driver from one system to another, the Export / Import menu item in the device editor is used. Via device editors menu *File -> Export...* the currently selected driver is exported to a file.

In the save dialog enter / select a file name and click Save.

This is also used to move new device drivers to the Devices.rsd database, which has all the drivers shipped with V-Control. If you created a new device like in the examples above, then this device exists only in your project file. Export it and the import it in the Devices.rsd by selecting *Configure -> Edit Device Templates*. Then import the new device.

## Import Device Driver

To transfer a driver from one system to another, the Export / Import menu item in the device editor is used. The Import menu item is available only if the device editor is launched via *Configure -> Edit Device Templates* The *File -> Import* command imports a previously exported driver. A dialog box asks for the name of the new driver.

# Device Drivers

The following chapters provide information for some device drivers shipped with V-Control. These drivers are used for special tasks.

---

## System

The *System* device is used to provide Time and Date information.

The screenshot displays the V-Control software interface. On the left, a 'Devices' list includes 'System\_v4', 'RemoteScreenReceiver\_v4', 'RemoteScreenSender\_v4', 'ioLogic\_E1214\_v4', 'PanasonicPT\_Series', 'EpsonProjector', and 'DVS\_Pronto'. The 'System\_v4' device is selected. To its right, a table shows variables and their values: 'Received' (empty), 'CurrentTime' (14:48:33:23), 'DayOfWeek' (7), 'DayOfMonth' (25), 'Month' (11), and 'Year' (2017). On the right side of the interface, the 'Device' tab is active, showing a 'Commands' list (empty) and a 'Setup' tab. At the bottom right, there are buttons for 'Add Cmd', '?', and 'Run Cmd'.

*It has no commands and does not need a channel, because all the communication is internal.*

# V-Control Connectors

For some devices not direct accessible by V-Control, we provide V-Control connectors. A V-Control connector is a piece of software that controls the device native and provides a network interface to connect to other software products such as V-Control.

So the V-Control connector does all the communication with a device internally and provides a simple control protocol via network to communicate with V-Control. This also has the advantage that devices not available via network now network controllable. The V-Control connector is running on a computer where the device is connected to (typically via USB). This can be the same machine where V-Control is running, but doesn't have to.

So if you need to control a midi device for example, and this device is far away from your V-Control machine, then you can use an additional computer with a MIDI interface and the V-Control Connector software installed near the MIDI device. V-Control then opens a TCP connection to this machine and from V-Controls point of view this is the MIDI interface.

---

## MIDI

There is no native support for USB MIDI devices in V-Control, but we have a nice work workaround. The TCP MIDI Connector interfaces between V-Control and your USB MIDI Device.


**Note:** This also works with rtpMIDI devices if a rtpMIDI driver is installed on your system.

To connect to the TCP MIDI Connector create a channel with the following specifications:

**Channel Type:** TCP Client

**Port:** 10002


**IP Address:** IP Address of the system with the TCP MIDI Connector (could be 127.0.0.1 if on the same machine then V-Control)



The TCP MIDI Connector is a Java software. On Windows, we provide a package with Java included, this is the reason why the zip file is relatively big. On other platforms you must install Java first.

Launch MIDITCP. In the left dropdown box, select the MIDI input. Use the right box for MIDI output. Once a MIDI Input and Output is selected, the configuration is finished. The software remembers the Input and Output and will use these interfaces net time it starts.

On the V-Control side, now use the TCP\_MIDI\_Connector\_v4 driver.





The driver has a couple of device variables that can be used to fire events if a MIDI message is received.

## Art-Net


V-Control has a very basic native Art-Net Support (Driver Art-Net\_v4). For more complex Art-Net / DMX Commands, we have the TCP Art-Net Connector.

As other V-Control Connectors, the TCP Art-Net Connector is a Software that can run on the same machine as V-Control, but also on a machine somewhere in the network. The last option might be useful if you have to control a huge number of Art-Net universes and channels.

**A maximum of 256 universes is supported.**

TCP Art-Net Connector runs on Windows 64 Bit, Linux 64 Bit and Raspberry Pi (Model 2 and 3).

## Main GUI



The left list shows the output values of the currently selected output universe. To change the universe, change the value in the *Out Universe* textbox. To change a value, select the channel in the channel(s) column and use the slider. Alternatively click in the value column to change it.

Double click the Channel number to enter a name here. Naming DMX channels is very helpful during programming to remember what a channel is used for.

The DMX values of the currently selected input universe are shown in the right listbox. Here you can select the universe by the *In Universe* textbox.

The listbox in the middle shows the available scenes. A scene is a complete set of DMX values and can contain up to 256 universes. Scenes can be created from output or input values.

The *Maximum Number of Universes* reduces the bandwidth on the network output. Here you can select how many of the 256 universes you will use. It starts always by 0, so if 10 is entered here, universes 0-9 can be used.

## Preferences

**Preferences**

**V-Control Interface**

192.168.1.59

Port: 10003

**Art-Net Interface**

192.168.1.59

☒ Send only Changed Universes

Send Rate(ms)

40

☒ Show DMX In and Out Values

**Art-Net Target Nodes**

Universe	Target IP
0	255.255.255.255
1	192.168.1.25
2	
3	
4	
5	
6	
7	
8	
9	
10	
11	
12	
13	
14	
15	
16	
17	
18	
19	
20	
21	
22	
23	
24	
25	
26	
27	
28	

**Monitor Channels**

Universe	Channel
001	001
001	002
001	003
001	004
001	005
001	006
001	007
001	008
001	009
001	010
001	011
001	012

Universe Start Channel End Channel

1 1 12

Add Monitor Channels

Delete selected Channels

Cancel OK

If the system that is running the TCP Art-Net Connector has more than one network interface, it is a good idea to use different interfaces for Art-Net and V-Control communication. Select the V-Control interface in the *V-control Interface* drop down box. The Art-Net interface is selected in the *Art-Net Interface* drop

down box. **ATTENTION:** because the network interface is bound to a specific IP address, 127.0.0.1 (localhost) will not work as V-Control channel, even if the TCP Art-Net connector is running locally on the V-Control machine.

The *Send only changed Universes* checkbox works as follows: If any of the universes that have a valid IP address have changed its content (DMX values), then these universes will be sent. In this case, the TCP Art-Net Connector sends only if something has changed, and only those universes that have changes in. If nothing has changed nothing will be sent. For most modern Art-Net devices this is OK, however, if the Art-Net devices you are controlling needs permanent DMX values, then uncheck this.

The *Send Rate (ms)* determines the update frequency of DMX values. The default is 40 ms, which equals 25 frames per second.

The *Show DMX In and Out Values* checkbox determines if the DMX values will be shown in the main GUI. Because of the underlying XOJO Framework, GUI updates are CPU expensive. On Raspberry Pi, this should only be checked for testing and maintenance.


### **Art-Net target Nodes**

This list is important. For each universe, we need a valid IP address here. If a universe has no IP address assigned, it will not send or receive anything. To reduce the bandwidth on your network you should use unicast here if possible (universe 1 in the screenshot above makes use of it). For broadcasting, use the broadcast address of your network (universe 0 in the screenshot above). Multiple Art-Net Targets can have the same IP Address. If you have an Art-Net node with 4 universes, then all these 4 universes will have the same IP address.

### **Monitor Channels**

TCP Art-Net Connector can send notifications to V-Control if a DMX value has changed. This can be used to trigger V-Control by Art-Net. To reduce the bandwidth and processing load for V-Control to the minimum that is needed, you have to select the DMX channels for monitoring. Enter the universe of the monitor channels in the *Universe* textbox, and then the *Start Channel* and *End Channel*. Finally click the *Add Monitor Channels* button. To delete Monitor Channels, select them in the listbox and click the *Delete selected Channels* button.

## New Scene from Output



To create a scene from output, select a universe in the *Out Universe:* textfield. Then select the channels you want to change in the left listbox. **Make sure to click the channel number, not the value.** Now move the slider to the position you need. This procedure is good if you want to set more then one channel to the same value. If you need individual DMX values for the channels then you can enter the value directly by clicking on the value. Alternatively you canm select other channels by selecting then and use the slider.

If more then one universe is involved in the scene, then change the universe and proceed like you did before. If all channels of all universes are set, click the *New Scene from Output* button. A new scene is added to the list. By default, the scene name is the same as the scene ID. Change the scene name by Double clicking it and enter a meaningful name.

The fade Time for a scene is entered by double clicking the *Time* column. Enter here the time in ms.

## New Scene from Input

Creating scenes from Output will not work good on a complex DMX show. For that reason, TCP Art-Net Connector can create scenes from input. In this case you capture the output of a light controller / desk. Press the *New Scene from Input* button to create a new scene. The scene captures all values of all universes that are send to the TCP Art-Net connector.

## Use with V-Control

Devices	Var Name	Value
Art-Net_TCP_Connector_v...	CH_Status	Connected
	Received	
	CH001	
	CH002	
	CH003	
	CH004	
	CH005	
	CH006	
	CH007	
	CH008	
	CH009	
	CH010	
	CH011	
	CH012	
	CH013	
	CH014	
	CH015	
	CH016	

Pos	Commands
020	SetChannels
050	PlayScene
050	PlayScene2

Universe: 0  
Channels (csv): 1,2,3,4,5,6,7,8,9,10  
Values (csv): 25,50,75,100,100,25,25,10,0  
FadeTime: 0

Add Cmd ? Run Cmd

To use TCP Art-Net Connector we need a TCP channel for communication.

**ATTENTION:** because the network interface is bound to a specific IP address, 127.0.0.1 (localhost) will not work as V-Control channel, even if the TCP Art-Net connector is running locally on the V-Control machine. You always need to enter the real IP address.

The Device has 512 Device Variables, one for each DMX channel. If the TCP Art-Net connector detects a value change on one of the selected Monitor Channels, the Device Variables for those Channels are updated and can be used as Event Trigger.

The *SetChannels* command is used to set some DMX channels to a new value. Select the Universe in the *Universe* field. Enter the DMX channels involved in the command as comma separated list (csv) in the *Channels (csv)* field. Then enter a DMX value for each channel, also as csv list. The *Fade Time* determines the duration that is used to fade these channels from their current value to the final value.


The *Play Scene* command uses a drop down box to select a scene that is available in the TCP Art-Net Connector. The available scenes are updated automatically every 3 seconds by a monitor command.

*Play Scene2* does the same then *Play Scene*, the difference is that you have to enter the scene name in a textfield.

# Tools

## Hex/Bin/Dec/ASCII conversion

The Hex/Bin/Dec/ASCII Tool (available via main menu *Tools* -> *Hex/Bin/Dec/ASCII/Calc*) converts data from one of the four formats to all other.



The screenshot shows a window titled "Hex/Bin/ASCII Calc" with a standard Windows title bar (minimize, maximize, close buttons). The window contains four input fields and four corresponding buttons:

- Binary:** Input field contains "1010", button "From Binary".
- Hex:** Input field contains "0A", button "From Hex" (highlighted with a blue border).
- Decimal:** Input field contains "10", button "From Decimal".
- ASCI:** Input field is empty, button "From ASCII".

*To convert e.g the hex number 4142, enter the number in the Hex field and click the From Hex button. As result, the hex value is shown in binary, decimal and ASCII representation.*

# Remote Protocol

A V-Control system that offers its service via network or RS232 communication is called a node. Via this service, nodes can communicate with other nodes or applications. The service give access to the tasks and attached devices. V-Control services are available via TCP, UDP, RS232 and, thanks to the build in webserver, HTTP. The communication protocol for TCP, UDP and RS232 connections is the same, the HTTP protocol differs a little.

To enable one or more of the services, see the V-Control Options chapter.

## TCP, UDP and RS232 Message Format

Start of Transmission	MSG Type (as string)	Separator	CMD ( as string)	Separator	Parameter (as string)	End of Transmission
Chr(4)	0=command 1=result 2=event 3=ProgressMSG	chr(5)	command string	chr(5)	strings separated by chr(2)	Chr(6)

## Websocket Message Format

There are two valid ways to control V-Control via web interface. The first one is to use a link in the page such as `<a href="/cgi-bin/scrRunTask%05AllLightsOff" target="ack">All LightsOff</a>`. This is very convinient if a simple GUI is needed. For complex, self updating GUIs the best solution is to use Websockets. The built in V-Control web server supports websockets from version 3.8 and later.

Start of Transmission	MSG Type (as string)	Separator	CMD ( as string)	Separator	Parameter (as string)	End of Transmission
%04	0=command 1=result 2=event 3=ProgressMSG	%05	command string	%05	strings separated by %02	%06

### Start of Transmission

The beginning of a new message is always \$H04 or ASCII Code 4. If used in http protocol, this the `"/cgi-bin/"` string is used instead (see Examples).

## Msg Type

ID	Description
	Command, a message was sent from the client to the Server (V-Control).
1	Result, this message contain the result of a client's request. The Data is stored in the Parameter Field.
2	Event, the server sent a message without a leading client request.
3	ProgressMSG, the server sent a message that contain a progress status

## Separator

The ASCII code 5 (\$H05 in hex.) separates the individual parts of the message. If using http, the separator is the string "%05".

## CMD

The Command sent to the server.

## Parameter

Parameters used by the command (optional in some cases)

## End of Transmission

The end of a message is always \$H06 or ASCII Code

## Web Interface

The connection from the html page to a task or command is made by a link. Usually, a link is used to navigate to another web page. Clicking on a link opens a new browser window, or replaces the current windows content with the linked page. But if we make a link to a task, there is no web page returned (and we do not want this). The task is launched and the return is only an acknowledge, saying that the task is executed or not. So we have to take care that the acknowledge message is not replacing our current browser content. One solution is to work with frames.

Frames divide a web page into two or more sections. In this example, we have 2 sections (frames). The ack frame is a located at the bottom with 30 pixel height, the main frame uses the remaining space at the top of the ack frame. The frame definition is done in the file index.html, located in V-Control httpRoot folder. index.html is the page that is shown if you type the V-Control web server url in your browser (i.e. http://192.168.1.45:8080). The listing below shows the content of index.html.



```

<!DOCTYPE HTML PUBLIC "-//W3C//DTD HTML 4.01 Frameset//EN"
"http://www.w3.org/TR/html4/frameset.dtd">
<html>
<head>
<title>V-Control Web Example</title>
</head>
<frameset rows="*,30">
<frame src="main.html" name="main">
<frame src="ack.html" name="ack">
<noframes>
  <body>

    </body>
</noframes>
</frameset>
</html>

```

The definition of the two frames is done by `<frameset rows="*,30">`, saying that the bottom frame is using 30 pixel, and the top frame the remaining space. Then, the top frame is linked to the file `main.html`, and its name is set to "main". The bottom frame is linked to `ack.html` and its name is set to `ack`. Via this name, the frame is accessible as target for a link. The page (file) `main.html` can contain a link to a task, and set the target for this link to `ack`.

```

<a href="cgi-bin/scrRunTask%05AllLightsOff" target="ack">All
LightsOff</a>

```

The link refers to the directory `cgi-bin`, which is a virtual directory. All links to this directory are interpreted as command. A task with the name "AllLightsOff" is called. Notice that the target is set to `ack`. The browser will show the result of the command in the frame `ack`. The "%05" is used as separator between the command (`scrRunTask`) and the parameter (`AllLightsOff`). If a command has more than one parameter, the parameters are separated by "%02".

If you like more information about html coding have a look at <http://www.htmlcodetutorial.com> and <http://www.w3schools.com> .

## HTTP Message Format

Start of Transmission	CMD ( as string)	Separator	Parameter (as string)
/cgi-bin/	command string	%05	strings separated by %02

# Examples

## TCP/UDP/RS232 Examples

To launch a task (Script or Cuelist) the scrRunTask comand is used. In the example below the name of the task we want to launch is “ExampleTask”.

### in Basic

```
Dim CMD As String
```

```
CMD = Chr(4)+"0"+Chr(5)+"scrRunTask"+Chr(5)+"ExampleTask"+Chr(6)
```

### in Delphi / Pascal

```
var
```

```
cmd: string;
```

```
cmd := Chr(4)+'0'+Chr(5)+'scrRunTask'+Chr(5)+'ExampleTask'+Chr(6);
```

As result, the node send an acknowledge message.

Chr(4)	1	chr(5)	scrRunTas k	chr(5)		Chr(6)
--------	---	--------	----------------	--------	--	--------

## HTTP Examples

To launch a task (Script or Cuelist) via web browser, a link to the /cgi-bin/ directory attached by the command is made. The html file must be copied in the Webservers Document directory. It is then available at [http://NodeAddress/](http://NodeAddress/Filename.htm)Filename.htm. The complete example file is listed below.

```
<html>
<head>
<title>Remote</title>
</head>
<body>
<a href="/cgi-bin/scrRunTask%05wait1" name="ExampleTask"
target="anyFrame"><h1>Wailt1</h1></a>
</body>
</html>
```

## Device Manager

CMD	Parameter	Result
devGetDeviceList		List of available Devices separated by chr(2)
devGetChannelList	DeviceName	List of channels associated with this device seperated by “,”

DevGetDeviceProperties	DeviceName	ID+chr(2)+DriverName+chr(2)+Name+chr(2)+Category+chr(2)+Helptext+chr(2)+Script+chr(2)+DP1Name+chr(2)+DP1GUIType+chr(2)+DP1MinMaxDef+chr(2)+DP1Default+chr(2)+DP1Mask+chr(2)+DP2Name+chr(2)+DP2GUIType+chr(2)+DP2MinMaxDef+chr(2)+DP2Default+chr(2)+DP2Mask+chr(2)+Manufactor+chr(2)+DeviceGUI
devGetCommandList	DeviceName	List of available commands of the selected device separated by chr(2)
devGetCommandProperties	DeviceName(2)CommandName	CommandName+chr(2)+Position+chr(2)+Script+chr(2)+TabID+chr(2)+P1Name+chr(2)+P1GUIType+chr(2)+P1MinMaxDef+chr(2)+P1Mask+chr(2)+P1Default+chr(2)+P2Name+chr(2)+P2GUIType+chr(2)+P2MinMaxDef+chr(2)+P2Mask+chr(2)+P2Default+chr(2)+P3Name+chr(2)+P3GUIType+chr(2)+P3MinMaxDef+chr(2)+P3Mask+chr(2)+P3Default+chr(2)+P4Name+chr(2)+P4GUIType+chr(2)+P4MinMaxDef+chr(2)+P4Mask+chr(2)+P4Default+chr(2)+Timeout+chr(2)+AckCmd+chr(2)+NextCmd+chr(2)+AckString+chr(2)+AckLen
devRunCommand	DeviceName(2)ChannelList(2)Command(2)DP1(2)DP2(2)P1(2)P2(2)P3(2)P4	DeviceName(2)ChannelList(2)Command(2)DP1(2)DP2(2)P1(2)P2(2)P3(2)P4(2)Ack

# Script Manager

<b>CMD</b>	<b>Parameter</b>	<b>Result</b>	<b>Example</b>
scrGetTasks		List of available tasks separated by chr(2)	(4)0(5)scrGetTasks(5)Task1(2)Task2(2).....Taskn(6)
scrRunTask	Task Name	"0" if successful or Error Number	(4)0(5)scrRunTask(5)TaskName(6)
scrStopTask	Task Name	"0" if successful	(4)0(5)scrStopTask(5)TaskName(6)
scrSetGlobalVar	VarName(2)Value	"0" if successful	
scrGetGlobalVar	VarName	Var Value	

<b>CMD</b>	<b>Parameter</b>	<b>Result</b>	<b>Example</b>
plsUp		Move up	(4)0(5)plsUp(5)(6)
plsDown		Move down	(4)0(5)plsDown(5)(6)
plsFire		Fire selected Task	(4)0(5)plsFire(5)(6)

# Change Log

## Version 4.6 (JUNE-2018)

- Add new Device variable Sent (shows the last command string)
- Help now works again showing the help file with the default pdf viewer
- Bugfix: SingleToStr function now works correct in Linux (MemoryBlock.LittleEndian = true)
- Bugfix: FloatStringToStr function now works correct in Linux (MemoryBlock.LittleEndian = true)
- Bugfix: Device Variable update was sometimes broken
- Driver Update: TCP MIDI Connector now works better with high Midi traffic
- Driver Update: Moxa ioLogic now has additional device variables showing the counter value if inputs are configured as counter
- New feature: The Engine Status Refresh Timer is now adjustable from 1 to 500 ms
- Added Reconnect Timer for UDP Sockets that fire in case of Error
- Change: precompiler Messages are now shown in status bar instead of Splash Screen
- Added MaximumBuffer option. If the ReceiveBuffer of a channel exceeds this amount then the buffer is cleared
- Added new DeviceVariable CH\_Status which shows the channel status (open, close, error etc.)
- New Driver: TCP Art-Net Connector
- New Connector: TCP Art-Net Connector supports up to 256 universes and capturing scenes from input

## Version 4.4 (MAY-2018)

- GUI: Message shows "Not in Run Mode" if a task is started without being in Run Mode
- GUI: Added Toolbar Button for Countdown Window
- GUI: Toolbar now shows correctly on High DPI Screens on Windows
- IOManagaer: IOMan.OnTimerSendAction: if Globals.EnableEvents = False then remove all ioCommands
- IOManager: Incomming Data is now buffered before processd. The Buffer is read by a timer triggered function now.
- ScriptManager: Endless repeats don't let System hang on Stop (Added "If Cancel then return" to Interpreter.bas)
- New Driver: Onvif TCP Connector
- New Driver: Art-Net
- New Driver: MIDI TCP Connector

## **Version 4.3 (FEB-2018)**

- Create Condition Template uses Variant as Default Event Variable Type
- Options->Remote is visible now
- Resolved: V-Control could freeze if a TCP connection is lost
- Device Variable Received now shows "TCP Closed" if a TCP Channel is not open for reading / writing
- New Options -> Show Engine Status Settings that enables / Disables Engine EventMessage Stack, IOQueue and Pending Acks values
- Delay now works more precise

## **Version 4.0 (NOV-2017)**

*V-Control 4.0 comes with a new redesign of the control engine and an updated user interface.*